

Bright Cluster Manager 8.2

User Manual

Revision: dfa5bdc

Date: Tue May 20 2025



©2020 Bright Computing, Inc. All Rights Reserved. This manual or parts thereof may not be reproduced in any form unless permitted by contract or by written permission of Bright Computing, Inc.

Trademarks

Linux is a registered trademark of Linus Torvalds. PathScale is a registered trademark of Cray, Inc. Red Hat and all Red Hat-based trademarks are trademarks or registered trademarks of Red Hat, Inc. SUSE is a registered trademark of Novell, Inc. PGI is a registered trademark of NVIDIA Corporation. FLEXlm is a registered trademark of Flexera Software, Inc. PBS Professional, PBS Pro, and Green Provisioning are trademarks of Altair Engineering, Inc. All other trademarks are the property of their respective owners.

Rights and Restrictions

All statements, specifications, recommendations, and technical information contained herein are current or planned as of the date of publication of this document. They are reliable as of the time of this writing and are presented without warranty of any kind, expressed or implied. Bright Computing, Inc. shall not be liable for technical or editorial errors or omissions which may occur in this document. Bright Computing, Inc. shall not be liable for any damages resulting from the use of this document.

Limitation of Liability and Damages Pertaining to Bright Computing, Inc.

The Bright Cluster Manager product principally consists of free software that is licensed by the Linux authors free of charge. Bright Computing, Inc. shall have no liability nor will Bright Computing, Inc. provide any warranty for the Bright Cluster Manager to the extent that is permitted by law. Unless confirmed in writing, the Linux authors and/or third parties provide the program as is without any warranty, either expressed or implied, including, but not limited to, marketability or suitability for a specific purpose. The user of the Bright Cluster Manager product shall accept the full risk for the quality or performance of the product. Should the product malfunction, the costs for repair, service, or correction will be borne by the user of the Bright Cluster Manager product. No copyright owner or third party who has modified or distributed the program as permitted in this license shall be held liable for damages, including general or specific damages, damages caused by side effects or consequential damages, resulting from the use of the program or the un-usability of the program (including, but not limited to, loss of data, incorrect processing of data, losses that must be borne by you or others, or the inability of the program to work together with any other program), even if a copyright owner or third party had been advised about the possibility of such damages unless such copyright owner or third party has signed a writing to the contrary.

Table of Contents

Table of Contents	i
0.1 About This Manual	v
0.2 Getting User-Level Support	v
1 Introduction	1
1.1 What Is A Beowulf Cluster?	1
1.1.1 Background And History	1
1.1.2 Brief Hardware And Software Description	1
1.2 Brief Network Description	2
2 Cluster Usage	3
2.1 Login To The Cluster Environment	3
2.2 Setting Up The User Environment	4
2.3 Environment Modules	4
2.3.1 Available commands	4
2.3.2 Changing The Current Environment	5
2.3.3 Changing The Default Environment	6
2.4 Compiling Applications	7
2.4.1 Open MPI And Mixing Compilers	8
3 Using MPI	9
3.1 Interconnects	9
3.1.1 Gigabit Ethernet	10
3.1.2 InfiniBand	10
3.2 Selecting An MPI implementation	10
3.3 Example MPI Run	10
3.3.1 Compiling And Preparing The Application	10
3.3.2 Creating A Machine File	11
3.3.3 Running The Application	11
3.3.4 Hybridization	13
3.3.5 Support Thread Levels	15
3.3.6 Further Recommendations	15
4 Workload Management	17
4.1 What Is A Workload Manager?	17
4.2 Why Use A Workload Manager?	17
4.3 How Does A Workload Manager Function?	17
4.4 Job Submission Process	18
4.5 What Do Job Scripts Look Like?	18
4.6 Running Jobs On A Workload Manager	18
4.7 Running Jobs In Cluster Extension Cloud Nodes Using <code>cmsub</code>	19
4.7.1 Options For <code>cmsub</code>	19

5	Slurm	21
5.1	Loading Slurm Modules And Compiling The Executable	21
5.2	Running The Executable With <code>salloc</code>	22
5.2.1	Node Allocation Examples	22
5.3	Running The Executable As A Slurm Job Script	24
5.3.1	Slurm Job Script Structure	24
5.3.2	Slurm Job Script Options	24
5.3.3	Slurm Environment Variables	25
5.3.4	Submitting The Slurm Job Script	26
5.3.5	Checking And Changing Queued Job Status	26
6	SGE	27
6.1	Writing A Job Script	27
6.1.1	Directives	27
6.1.2	SGE Environment Variables	27
6.1.3	Job Script Options	28
6.1.4	The Executable Line	29
6.1.5	Job Script Examples	30
6.2	Submitting A Job	31
6.2.1	Submitting To A Specific Queue	31
6.2.2	Queue Assignment Required For <code>cm-scale</code>	32
6.3	Monitoring A Job	32
6.4	Deleting A Job	33
7	PBS Variants: Torque And PBS Pro	35
7.1	Components Of A Job Script	35
7.1.1	Sample Script Structure	36
7.1.2	Directives	36
7.1.3	The Executable Line	39
7.1.4	Example Batch Submission Scripts	39
7.1.5	Links To Other Resources About Job Scripts In Torque And PBS Pro	41
7.2	Submitting A Job	41
7.2.1	Preliminaries: Loading The Modules Environment	41
7.2.2	Using <code>qsub</code>	41
7.2.3	Job Output	42
7.2.4	Monitoring A Job	42
7.2.5	Deleting A Job	45
7.2.6	Monitoring Nodes In Torque And PBS Pro	45
8	Using GPUs	47
8.1	Packages	47
8.2	Using CUDA	48
8.3	Using OpenCL	48
8.4	Compiling Code	48
8.5	Available Tools	49
8.5.1	CUDA <code>gdb</code>	49
8.5.2	<code>nvidia-smi</code>	49

8.5.3	CUDA Utility Library	50
8.5.4	CUDA “Hello world” Example	51
8.5.5	OpenACC	52
9	Using Kubernetes	53
9.1	Introduction To Kubernetes Running Via Bright Cluster Manager	53
9.2	Kubernetes Quickstarts	53
9.2.1	Quickstart: Accessing The Kubernetes Dashboard	54
9.2.2	Quickstart: Using kubectl From A Local Machine	56
9.2.3	Quickstart: Submitting Batch Jobs With kubectl	57
9.2.4	Quickstart: Persistent Storage For Kubernetes Using Ceph	58
9.2.5	Quickstart: Helm, The Kubernetes Package Manager	60
10	Spark On Kubernetes	61
10.0.1	Important Requirements	61
10.0.2	Using spark-submit To Submit A Job	61
10.0.3	Submitting A Python Job With spark-submit	63
10.0.4	Running A PySpark Notebook In JupyterHub	63
10.0.5	How To Build A Custom Docker Image	64
10.0.6	Mounting Volumes Into Containers	65
11	Using Singularity	69
11.1	How To Build A Simple Container Image	69
11.2	Using MPI	72
11.3	Using A Container Image With Workload Managers	73
11.4	Using the singularity Utility	73
12	User Portal	75
12.1	Overview Page	75
12.2	Workload Page	76
12.3	Nodes Page	77
12.4	OpenStack Page	78
12.5	Kubernetes Page	79
12.6	Charts Page	80
13	Running Spark Jobs	83
13.1	What Is Spark?	83
13.2	Spark Usage	83
13.2.1	Spark And Hadoop Modules	83
13.2.2	Spark Job Submission With spark-submit	83
14	Using OpenStack	87
14.1	User Access To OpenStack	87
14.2	Getting A User Instance Up	87
14.2.1	Making An Image Available In OpenStack	88
14.2.2	Creating The Networking Components For The OpenStack Image To Be Launched	89
14.2.3	Accessing The Instance Remotely With A Floating IP Address	92

A	MPI Examples	99
A.1	“Hello world”	99
A.2	MPI Skeleton	100
A.3	MPI Initialization And Finalization	102
A.4	What Is The Current Process? How Many Processes Are There?	102
A.5	Sending Messages	102
A.6	Receiving Messages	102
A.7	Blocking, Non-Blocking, And Persistent Messages	103
A.7.1	Blocking Messages	103
A.7.2	Non-Blocking Messages	103
A.7.3	Persistent, Non-Blocking Messages	104
B	Compiler Flag Equivalence	105

Preface

Welcome to the *User Manual* for Bright Cluster Manager 8.2.

0.1 About This Manual

This manual is intended for the end users of a cluster running Bright Cluster Manager, and tends to see things from a user perspective. It covers the basics of using the Bright Cluster Manager user environment to run compute jobs on the cluster. Although it does cover some aspects of general Linux usage, it is by no means comprehensive in this area. Readers are expected to have some familiarity with the basics of a Linux environment from the regular user point of view.

Regularly updated production versions of the Bright Cluster Manager 8.2 manuals are available on updated clusters by default at `/cm/shared/docs/cm`. The latest updates are always online at <http://support.brightcomputing.com/manuals>.

The manuals constantly evolve to keep up with the development of the Bright Cluster Manager environment and the addition of new hardware and/or applications. The manuals also regularly incorporate customer feedback. Administrator and user input is greatly valued at Bright Computing. So any comments, suggestions or corrections will be very gratefully accepted at manuals@brightcomputing.com.

There is also a feedback form available via Bright View for administrators, via the Account icon, , following the clickpath:

Account→Help→Feedback

0.2 Getting User-Level Support

A user is first expected to refer to this manual or other supplementary site documentation when dealing with an issue. If that is not enough to resolve the issue, then support for an end-user is typically provided by the cluster administrator, who is often a unix or Linux system administrator with some cluster experience. Commonly, the administrator has configured and tested the cluster beforehand, and therefore has a good idea of its behavior and quirks. The initial step when calling in outside help is thus often to call in the cluster administrator.

1

Introduction

This manual is intended for cluster users who need a quick introduction to the Bright Cluster Manager, which manages a Beowulf cluster configuration. It explains how to use the MPI and batch environments, how to submit jobs to the queuing system, and how to check job progress. The specific combination of hardware and software installed may differ depending on the specification of the cluster, which means that parts of this manual may not be relevant to the user's particular cluster.

1.1 What Is A Beowulf Cluster?

1.1.1 Background And History

In the history of the English language, Beowulf is the earliest surviving epic poem written in English. It is a story about a hero with the strength of many men who defeated a fearsome monster called Grendel.

In computing, a Beowulf class cluster computer is a multiprocessor architecture used for parallel computations, i.e., it uses many processors together so that it has the brute force to defeat certain “fear-some” number-crunching problems.

The architecture was first popularized in the Linux community when the source code used for the original Beowulf cluster built at NASA was made widely available. The Beowulf class cluster computer design usually consists of one head node and one or more regular nodes connected together via Ethernet or some other type of network. While the original Beowulf software and hardware has long been superseded, the name given to this basic design remains “Beowulf class cluster computer”, or less formally “Beowulf cluster”.

1.1.2 Brief Hardware And Software Description

On the hardware side, commodity hardware is generally used in Beowulf clusters to keep costs down. These components are usually x86-compatible processors produced at the Intel and AMD chip foundries, standard Ethernet adapters, InfiniBand interconnects, and switches.

On the software side, free and open-source software is generally used in Beowulf clusters to keep costs down. For example: the Linux operating system, the GNU C compiler collection and open-source implementations of the Message Passing Interface (MPI) standard.

The head node controls the whole cluster and serves files and information to the nodes. It is also the cluster's console and gateway to the outside world. Large Beowulf clusters might have more than one head node, and possibly other nodes dedicated to particular tasks, for example consoles or monitoring stations. In most cases compute nodes in a Beowulf system are dumb—in general, the dumber the better—with the focus on the processing capability of the node within the cluster, rather than other abilities a computer might generally have. A node may therefore have

- one or more processing elements. The processors may be standard CPUs, as well as GPUs, FPGAs, MICs, and so on.
- enough local memory—memory contained in a single node—to deal with the processes passed on to the node

- a connection to the rest of the cluster

Nodes are configured and controlled by the head node, and do only what they are told to do. One of the main differences between Beowulf and a Cluster of Workstations (COW) is the fact that Beowulf behaves more like a single machine rather than many workstations. In most cases, the nodes do not have keyboards or monitors, and are accessed only via remote login or possibly serial terminal. Beowulf nodes can be thought of as a CPU + memory package which can be plugged into the cluster, just like a CPU or memory module can be plugged into a motherboard to form a larger and more powerful machine. A significant difference is that the nodes of a cluster have a relatively slower interconnect.

1.2 Brief Network Description

A Beowulf Cluster consists of a login, compile and job submission node, called the head, and one or more compute nodes, often referred to as worker nodes. A second (fail-over) head node may be present in order to take control of the cluster in case the main head node fails. Furthermore, a second fast network may also have been installed for high-performance low-latency communication between the (head and the) nodes (see figure 1.1).




Figure 1.1: Cluster layout

The login node is used to compile software, to submit a parallel or batch program to a job queuing system and to gather/analyze results. Therefore, it should rarely be necessary for a user to log on to one of the nodes and in some cases node logins are disabled altogether. The head, login and compute nodes usually communicate with each other through a gigabit Ethernet network, capable of transmitting information at a maximum rate of 1000 Mbps. In some clusters 10 gigabit Ethernet (10GE, 10GBE, or 10GigE) is used, capable of up to 10 Gbps rates.

Sometimes an additional network is used by the cluster for even faster communication between the compute nodes. This particular network is mainly used for programs dedicated to solving large scale computational problems, which may require multiple machines and could involve the exchange of vast amounts of information. One such network topology is InfiniBand, commonly capable of transmitting information at a maximum effective data rate of about 124Gbps and about $1.2\mu\text{s}$ end-to-end latency on small packets, for clusters in 2013. The commonly available maximum transmission rates will increase over the years as the technology advances.

Applications relying on message passing benefit greatly from lower latency. The fast network is usually complementary to a slower Ethernet-based network.

2

Cluster Usage

2.1 Login To The Cluster Environment

The login node is the node where the user logs in and works from. Simple clusters have a single login node, but large clusters sometimes have multiple login nodes to improve the reliability of the cluster. In most clusters, the login node is also the head node from where the cluster is monitored and installed. On the login node:

- applications can be developed
- code can be compiled and debugged
- applications can be submitted to the cluster for execution
- running applications can be monitored

To carry out an ssh login to the cluster, a terminal session can be started from Unix-like operating systems:

Example

```
$ ssh myname@cluster.hostname
```

On a Windows operating system, an SSH client such as PuTTY (<http://www.putty.org>) can be downloaded. Another standard possibility is to run a Unix-like environment such as Cygwin (<http://www.cygwin.com>) within the Windows operating system, and then run the SSH client from within it.

A Mac OS X user can use the Terminal application from the Finder, or under Application/Utilities/Terminal.app. X11 must be installed from the Mac OS X medium, or alternatively, XQuartz can be used instead. XQuartz is an alternative to the official X11 package, and is usually more up-to-date and less buggy.

When using the SSH connection, the cluster's address must be added. When the connection is made, a username and password must be entered at the prompt.

If the administrator has changed the default SSH port from 22 to something else, the port can be specified with the `-p <port>` option:

```
$ ssh -X -p <port> <user>@<cluster>
```

The `-X` option can be dropped if no X11-forwarding is required. X11-forwarding allows a GUI application from the cluster to be displayed locally.

Optionally, after logging in, the password used can be changed using the `passwd` command:

```
$ passwd
```

2.2 Setting Up The User Environment

By default, each user uses the bash shell interpreter. In that case, each time a user login takes place, a file named `.bashrc` is executed to set up the shell environment for the user. The shell and its environment can be customized to suit user preferences. For example,

- the prompt can be changed to indicate the current username, host, and directory, for example: by setting the prompt string variable:

```
PS1="\u@\h:\w ] $"
```

- the size of the command history file can be increased, for example: `export HISTSIZE=100`
- aliases can be added for frequently used command sequences, for example: `alias lart='ls -alrt'`
- environment variables can be created or modified, for example: `export MYVAR=MYSTRING`
- the location of software packages and versions that are to be used by a user (the path to a package) can be set.

Because there is a huge choice of software packages and versions, it can be hard to set up the right environment variables and paths for software that is to be used. Collisions between different versions of the same package and non-matching dependencies on other packages must also be avoided. To make setting up the environment easier, Bright Cluster Manager provides preconfigured environment modules (section 2.3).

2.3 Environment Modules

It can be quite hard to set up the correct environment to use a particular software package and version.

For instance, managing several MPI software packages on the same system or even different versions of the same MPI software package is quite difficult for most users on a standard SUSE or Red Hat system because many software packages use the same names for executables and libraries.

A user could end up with the problem of never being quite sure which libraries have been used for the compilation of a program as multiple libraries with the same name may be installed. Very often a user would like to test new versions of a software package before permanently installing the package. Within a Red Hat or SuSE setup without special utilities, this would be quite a complex task to achieve. Environment modules, using the `module` command, are a special utility to make this task much easier.

2.3.1 Available commands

```
$ module --help
```

```
Modules Release 3.2.10 2012-12-21 (Copyright GNU GPL v2 1991):
```

```
Usage: module [ switches ] [ subcommand ] [subcommand-args ]
```

Switches:

<code>-H --help</code>	this usage info
<code>-V --version</code>	modules version & configuration options
<code>-f --force</code>	force active dependency resolution
<code>-t --terse</code>	terse format avail and list format
<code>-l --long</code>	long format avail and list format
<code>-h --human</code>	readable format avail and list format
<code>-v --verbose</code>	enable verbose messages
<code>-s --silent</code>	disable verbose messages
<code>-c --create</code>	create caches for avail and apropos

```

-i|--icase           case insensitive
-u|--userlvl <lvl>  set user level to (nov[ice],exp[ert],adv[anced])
Available SubCommands and Args:
+ add|load           modulefile [modulefile ...]
+ rm|unload          modulefile [modulefile ...]
+ switch|swap        [modulefile1] modulefile2
+ display|show       modulefile [modulefile ...]
+ avail              [modulefile [modulefile ...]]
+ use [-a|--append]  dir [dir ...]
+ unuse              dir [dir ...]
+ update
+ refresh
+ purge
+ list
+ clear
+ help               [modulefile [modulefile ...]]
+ whatis             [modulefile [modulefile ...]]
+ apropos|keyword    string
+ initadd            modulefile [modulefile ...]
+ initprepend        modulefile [modulefile ...]
+ initrm             modulefile [modulefile ...]
+ initswitch         modulefile1 modulefile2
+ initlist
+ initclear

```

2.3.2 Changing The Current Environment

The modules loaded into the user's environment can be seen with:

```
$ module list
```

Modules can be loaded using the add or load options. A list of modules can be added by spacing them:

```
$ module add shared gcc openmpi/gcc
```

The shared module is special. If it is to be loaded, it is usually placed first in a list before the other modules, because the other modules often depend on it. The shared module is described further shortly.

The "module avail" command lists all modules that are available for loading (some output elided):

Example

```
[fred@bright82 ~]$ module avail
```

```

----- /cm/local/modulefiles -----
cluster-tools/8.2 dot          module-info      use.own
cmd                freeipmi/1.2.6  null           version
cmsh               ipmitool/1.8.12  openldap
cmsub/8.2          module-git       shared

----- /cm/shared/modulefiles -----
acml/gcc/64/5.3.1  hwloc/1.7
acml/gcc/fma4/5.3.1 intel-cluster-checker/2.0
acml/gcc/mp/64/5.3.1 intel-cluster-runtime/ia32/3.5
acml/gcc/mp/fma4/5.3.1 intel-cluster-runtime/intel64/3.5
acml/gcc-int64/64/5.3.1 intel-cluster-runtime/mic/3.5
acml/gcc-int64/fma4/5.3.1 intel-tbb-oss/ia32/41_20130314oss
...

```

In the list there are two kinds of modules:

- **local modules**, which are specific to the node, or head node only
- **shared modules**, which are made available from a shared storage, and which only become available for loading after the shared module is loaded.

The shared module is obviously a useful local module, and is therefore usually configured to be loaded for the user by default.

Although version numbers are shown in the “module avail” output, it is not necessary to specify version numbers, unless multiple versions are available for a module¹.

To remove one or more modules, the “module unload” or “module rm” command is used.

To remove all modules from the user’s environment, the “module purge” command is used.

The user should be aware that some loaded modules can conflict with others loaded at the same time. For example, loading openmpi/gcc without removing an already loaded openmpi/gcc can result in confusion about what compiler opencc is meant to use.

2.3.3 Changing The Default Environment

The initial state of modules in the user environment can be set as a default using the “module init*” subcommands. The more useful ones of these are:

- `module initadd`: add a module to the initial state
- `module initrm`: remove a module from the initial state
- `module initlist`: list all modules loaded initially
- `module initclear`: clear all modules from the list of modules loaded initially

Example

```
$ module initclear
$ module initlist
bash initialization file $HOME/.bashrc loads modules:
    null
$ module initadd shared gcc/4.8.1 openmpi/gcc sge
$ module initlist
bash initialization file $HOME/.bashrc loads modules:
    null shared gcc/4.8.1 openmpi/gcc/64/1.6.5 sge/2011.11p1
```

In the preceding example, the newly defined initial state module environment for the user is loaded from the next login onwards.

If the user is unsure about what the module does, it can be checked using “module whatis”:

```
$ module whatis sge
sge                : Adds sge to your environment
```

The man pages for module gives further details on usage.

¹For multiple versions, when no version is specified, the alphabetically-last version is chosen. This usually is the latest, but can be an issue when versions move from, say, 9, to 10. For example, the following is sorted in alphabetical order: v1 v10 v11 v12 v13 v2 v3 v4 v5 v6 v7 v8 v9.

2.4 Compiling Applications

Compiling an application is usually done on the head node or login node. Typically, there are several compilers available on the head node, which provide different levels of optimization, standards conformance, and support for accelerators. For example: GNU compiler collection, Intel compilers, and Portland Group compilers. The following table summarizes the available compiler commands on the cluster:

Language	GNU	Portland	Intel
C	gcc	pgcc	icc
C++	g++	pgCC	icc
Fortran77	gfortran	pgf77	ifort
Fortran90	gfortran	pgf90	ifort
Fortran95	gfortran	pgf95	ifort

GNU compilers are the de facto standard on Linux and are installed by default. They are provided under the terms of the GNU General Public License. Commercial compilers by Portland and Intel are available as packages via the Bright Cluster Manager YUM repository, and require the purchase of a license to use them. To make a compiler available to be used in a user's shell commands, the appropriate environment module (section 2.3) must be loaded first. On most clusters two versions of GCC are available:

1. The version of GCC that comes along with the Linux distribution. For example, for CentOS 6.x:

Example

```
[fred@bright82 ~]$ which gcc; gcc --version | head -1
/usr/bin/gcc
gcc (GCC) 4.4.7 20120313 (Red Hat 4.4.7-3)
```

2. The latest version suitable for general use that is packaged as a module by Bright Computing:

Example

```
[fred@bright82 ~]$ module load gcc
[fred@bright82 ~]$ which gcc; gcc --version | head -1
/cm/shared/apps/gcc/4.8.1/bin/gcc
gcc (GCC) 4.8.1
```

To use the latest version of GCC, the gcc module must be loaded. To revert to the version of GCC that comes natively with the Linux distribution, the gcc module must be unloaded.

The compilers in the preceding table are ordinarily used for applications that run on a single node. However, the applications used may fork, thread, and run across as many nodes and processors as they can access if the application is designed that way.

The standard, structured way of running applications in parallel is to use the MPI-based libraries, which link to the underlying compilers in the preceding table. The underlying compilers are automatically made available after choosing the parallel environment (MPICH, MVAPICH, Open MPI, etc.) via the following compiler commands:

Language	C	C++	Fortran77	Fortran90	Fortran95
Command	mpicc	mpiCC	mpif77	mpif90	mpif95

2.4.1 Open MPI And Mixing Compilers

Bright Cluster Manager comes with multiple Open MPI packages corresponding to the different available compilers. However, sometimes mixing compilers is desirable. For example, C-compilation may be preferred using `icc` from Intel, while Fortran90-compilation may be preferred using `gfortran` from the GNU Project. In such cases it is possible to override the default compiler path environment variable, for example:

```
[fred@bright82 ~]$ module list
Currently Loaded Modulefiles:
  1) null                      3) gcc/4.4.7                  5) sge/2011.11
  2) shared                    4) openmpi/gcc/64/1.4.5
[fred@bright82 ~]$ mpicc --version --showme; mpif90 --version --showme
gcc --version
gfortran --version
[fred@bright82 ~]$ export OMPI_CC=icc; export OMPI_FC=openf90
[fred@bright82 ~]$ mpicc --version --showme; mpif90 --version --showme
icc --version
openf90 --version
```

Variables that may be set are `OMPI_CC`, `OMPI_FC`, `OMPI_F77`, and `OMPI_CXX`. More on overriding the Open MPI wrapper settings is documented in the man pages of `mpicc` in the environment section.

3

Using MPI

The Message Passing Interface (MPI) is a standardized and portable message passing system designed by a group of researchers from academia and industry to function on a wide variety of parallel computers. The standard defines the syntax and semantics of a core of library routines useful to a wide range of users writing portable message-passing programs in Fortran or the C programming language. MPI libraries allow the compilation of code so that it can be used over a variety of multi-processor systems from SMP nodes to NUMA (non-Uniform Memory Access) systems and interconnected cluster nodes .

MPI libraries are MPICH (<https://www.mpich.org/>), MVAPICH (<http://mvapich.cse.ohio-state.edu/>), or OpenMPI (<https://www.open-mpi.org/>). The MPI libraries can be compiled with GCC, Intel, or PGI.

Depending on the cluster hardware, the interconnect available may be: Ethernet (GE), InfiniBand (IB), or Myrinet (MX).

Depending on the cluster configuration, MPI implementations for different compilers can be loaded. By default, MPI implementations that are installed are compiled and made available using GCC.

The interconnect and compiler implementation can be worked out from looking at the module and package name. The modules available can be searched through for the compiler variant, and then the package providing it can be found:

Example

```
[fred@bright82 ~]$ # search for modules starting with (open)mpi
[fred@bright82 ~]$ module -l avail | egrep '(\^openmpi|\^mpi)'
mpich/ge/gcc/64/3.3                                2018/12/20 11:09:10
openmpi/gcc/64/1.10.7                             2019/01/17 00:40:45
[fred@bright82 ~]$ rpm -qa | egrep '(\^mpi|\^openmpi)'
openmpi-geib-gcc-64-1.10.7-478_cm8.2.x86_64
mpich-ge-gcc-64-3.3-182_cm8.2.x86_64
```

Here, for example,

```
openmpi-geib-gcc-64-1.10.7-478_cm8.2.x86_64
```

implies: Open MPI version 1.10.7, compiled for both Gigabit Ethernet (ge) and InfiniBand (ib), with the GCC (gcc) compiler for a 64-bit architecture, packaged as a (Bright) cluster manager (cm) package, for version 8.2 of Bright Cluster Manager, for the x86_64 architecture.

3.1 Interconnects

Jobs can use particular networks for inter-node communication.

3.1.1 Gigabit Ethernet

Gigabit Ethernet is the interconnect that is most commonly available. For Gigabit Ethernet, no additional modules or libraries are needed. The Open MPI, MPICH and MVAPICH implementations will all work over Gigabit Ethernet.

3.1.2 InfiniBand

InfiniBand is a high-performance switched fabric which is characterized by its high throughput and low latency. Open MPI, MVAPICH and MVAPICH2 are suitable MPI implementations for InfiniBand.

3.2 Selecting An MPI implementation

Once the appropriate compiler module has been loaded, the MPI implementation is selected along with the appropriate library modules. In the following list, *<compiler>* indicates a choice of *gcc*, *intel*, or *pgi*:

- *mpich/ge/<compiler>*
- *mvapich2/<compiler>*
- *openmpi/<compiler>*
- *openmpi3/<compiler>*

After the appropriate MPI module has been added to the user environment, the user can start compiling applications. The *mpich* and *openmpi* implementations may be used on Ethernet. On InfiniBand, *mvapich*, *mvapich2* and *openmpi* may be used. Open MPI's *openmpi* implementation will first attempt to use InfiniBand, but will revert to Ethernet if InfiniBand is not available.

3.3 Example MPI Run

This example covers an MPI run, which can be run inside and outside of a queuing system.

To use *mpirun*, the relevant environment modules must be loaded. For example, to use the *mpich* over Gigabit Ethernet (*ge*) GCC implementation:

```
$ module add mpich/ge/gcc
```

or to use the *openmpi3* Open MPI v3 Intel implementation:

```
$ module add openmpi3/intel
```

Similarly, to use the *mvapich2* InfiniBand GCC implementation:

```
$ module add mvapich2/gcc
```

Depending on the libraries and compilers installed on the system, the availability of these packages might differ. To see a full list on the system the command “*module avail*” can be typed.

3.3.1 Compiling And Preparing The Application

The code must be compiled with MPI libraries and an underlying compiler. The correct library command can be found in the following table:

Language	C	C++	Fortran77	Fortran90	Fortran95
Command	<i>mpicc</i>	<i>mpiCC</i>	<i>mpif77</i>	<i>mpif90</i>	<i>mpif95</i>

An MPI application *myapp.c*, built in C, could then be compiled as:

```
$ mpicc myapp.c
```

The *a.out* binary that is created can then be executed using the *mpirun* command (section 3.3.3).

3.3.2 Creating A Machine File

A machine file contains a list of nodes which can be used by MPI programs.

The workload management system creates a machine file based on the nodes allocated for a job when the job is submitted with the workload manager job submission tool. So if the user chooses to have the workload management system allocate nodes for the job then creating a machine file is not needed.

However, if an MPI application is being run “by hand” outside the workload manager, then the user is responsible for creating a machine file manually. Depending on the MPI implementation, the layout of this file may differ.

Machine files can generally be created in two ways:

- Listing the same node several times to indicate that more than one process should be started on each node:

```
node001
node001
node002
node002
```

- Listing nodes once, but with a suffix for the number of CPU cores to use on each node:

```
node001:2
node002:2
```

3.3.3 Running The Application

A Simple Parallel Processing Executable

A simple “hello world” program designed for parallel processing can be built with MPI. After compiling it, it can be used to send a message about how and where it is running:

```
[fred@bright82 ~]$ cat hello.c
#include <stdio.h>
#include <mpi.h>

int main (int argc, char *argv[])
{
    int id, np, i;
    char processor_name[MPI_MAX_PROCESSOR_NAME];
    int processor_name_len;

    MPI_Init(&argc, &argv);

    MPI_Comm_size(MPI_COMM_WORLD, &np);
    MPI_Comm_rank(MPI_COMM_WORLD, &id);
    MPI_Get_processor_name(processor_name, &processor_name_len);

    for(i=1;i<2;i++)
    {printf(
    "Hello world from process %03d out of %03d, processor name %s\n",
    id, np, processor_name
    );}

    MPI_Finalize();
    return 0;
}

[fred@bright82 ~]$ module add openmpi/gcc    #or as appropriate
[fred@bright82 ~]$ mpicc hello.c -o hello
```

```
[fred@bright82 ~]$ ./hello
Hello world from process 000 out of 001, processor name bright82.cm.cluster
```

However, it still runs on a single processor unless it is submitted to the system in a special way.

Running An MPI Executable In Parallel Without A Workload Manager

Compute node environment provided by user's .bashrc: After the relevant module files are chosen (section 3.3) for MPI, an executable compiled with MPI libraries runs on nodes in parallel when submitted with `mpirun`. The executable running on other nodes loads environmental modules on those other nodes by sourcing the `.bashrc` file of the user (section 2.3.3). It is therefore important to ensure that the environmental module stack used on the compute node is clean and consistent.

Example

Supposing the `.bashrc` loads two MPI stacks—the `mpich` stack, followed by the Open MPI stack—then that can cause errors because the compute node may use parts of the wrong MPI implementation.

The environment of the user from the interactive shell prompt is not normally carried over automatically to the compute nodes during an `mpirun` submission. That is, compiling and running the executable will normally work only on the local node without a special treatment. To have the executable run on the compute nodes, the right environment modules for the job must be made available on the compute nodes too, as part of the user login process to the compute nodes for that job. Usually the system administrator takes care of such matters in the default user configuration by setting up the default user environment (section 2.3.3), with reasonable `initrm` and `initadd` options. Users are then typically allowed to set up their personal default overrides to the default administrator settings, by placing their own `initrm` and `initadd` options to the module command according to their needs.

Running `mpirun` outside a workload manager: When using `mpirun` manually, outside a workload manager environment, the number of processes (`-np`) as well as the number of hosts (`-machinefile`) should be specified. For example, on a cluster with 2 compute-nodes and a machine file as specified in section 3.3.2:

Example

```
[fred@bright82 ~]$ module initclear; module initadd openmpi/gcc
[fred@bright82 ~]$ module add openmpi/gcc #or as appropriate
[fred@bright82 ~]$ mpirun -np 4 -machinefile mpirun.hosts hello
Hello world from process 002 out of 004, processor name node002.cm.cluster
Hello world from process 003 out of 004, processor name node001.cm.cluster
Hello world from process 000 out of 004, processor name node002.cm.cluster
Hello world from process 001 out of 004, processor name node001.cm.cluster
```

The output of the preceding program is actually printed in random order. This can be modified as follows, so that only process 0 prints to the standard output, and other processes communicate their output to process 0:

```
#include "mpi.h"
#include "string.h"
#include <stdio.h>

int main( int argc, char *argv[] )
{
    int numprocs, myrank, namelen, i;
    char processor_name[MPI_MAX_PROCESSOR_NAME];
    char greeting[MPI_MAX_PROCESSOR_NAME + 80];
```

```

MPI_Status status;

MPI_Init( &argc, &argv );
MPI_Comm_size( MPI_COMM_WORLD, &numprocs );
MPI_Comm_rank( MPI_COMM_WORLD, &myrank );
MPI_Get_processor_name( processor_name, &namelen );

sprintf( greeting, "Hello world, from process %d of %d on %s",
        myrank, numprocs, processor_name );

if ( myrank == 0 ) {
    printf( "%s\n", greeting );
    for ( i = 1; i < numprocs; i++ ) {
        MPI_Recv( greeting, sizeof( greeting ), MPI_CHAR,
                i, 1, MPI_COMM_WORLD, &status );
        printf( "%s\n", greeting );
    }
}
else {
    MPI_Send( greeting, strlen( greeting ) + 1, MPI_CHAR,
            0, 1, MPI_COMM_WORLD );
}

MPI_Finalize( );
return 0;
}

```

```

fred@bright82 ~]$ module add mvapich/gcc #or as appropriate
fred@bright82 ~]$ mpirun -np 4 -machinefile mpirun.hosts hello
Hello world from process 0 of 4 on node001.cm.cluster
Hello world from process 1 of 4 on node002.cm.cluster
Hello world from process 2 of 4 on node001.cm.cluster
Hello world from process 3 of 4 on node002.cm.cluster

```

Running the executable with `mpirun` outside the workload manager as shown does not take the resources of the cluster into account. To handle running jobs with cluster resources is of course what workload managers such as Slurm are designed to do. Workload managers also typically take care of what environment modules should be loaded on the compute nodes for a job, via additions that the user makes to a job script.

Running an application through a workload manager via a job script is introduced in Chapter 4.

Appendix A contains a number of simple MPI programs.

3.3.4 Hybridization

OpenMP is an implementation of multi-threading. This is a method of parallelizing whereby a parent thread—a series of instructions executed consecutively—forks a specified number of child threads, and a task is divided among them. The threads then run concurrently, with the runtime environment allocating threads to different processors and accessing the shared memory of an SMP system.

MPI can be mixed with OpenMP to achieve high performance on a cluster/supercomputer of multi-core nodes or servers. MPI creates processes that reside on the level of node, while OpenMP forks threads on the level of a core within an SMP node. Each process executes a portion of the overall computation, while inside each process, a team of threads is created through OpenMP directives to further divide the problem. This kind of execution makes sense due to:

- the ease of programming that OpenMP provides

- OpenMP might not require copies of data structure, which allows for designs that overlap computation and communication
- overcoming the limits of parallelism within the SMP node is of course still possible by using the power of other nodes via MPI.

Example

```
#include<mpi.h>
#include <omp.h>
#include <stdio.h>
#include<stdlib.h>

int main(int argc , char** argv) {
    int size, myrank,namelength;
    char processor_name[MPI_MAX_PROCESSOR_NAME];
    MPI_Init(&argc,&argv);
    MPI_Comm_rank(MPI_COMM_WORLD,&myrank);
    MPI_Comm_size(MPI_COMM_WORLD,&size);
    MPI_Get_processor_name(processor_name,&namelength);
    printf("Hello I am Processor %d on %s of %d\n",myrank,processor_name,\
size);
    int tid = 0; int n_of_threads = 1;
    #pragma omp parallel default(shared) private(tid, n_of_threads)
    {
        #if defined (_OPENMP)
            n_of_threads= omp_get_num_threads();
            tid = omp_get_thread_num();
        #endif
        printf("Hybrid Hello World: I am thread # %d out of %d\n", tid, n_o\
f_threads);
    }
    MPI_Finalize();
    return 0;
}
```

To compile the program:

```
fred@bright82 ~]$ mpicc -o hybridhello omphello.c -fopenmp
```

To specify the number of OpenMP threads per MPI task the environment variable OMP_NUM_THREADS must be set.

Example

```
fred@bright82 ~]$ export OMP_NUM_THREADS=3
```

The number of threads specified by the variable can then be run over the hosts specified by the mpirun.hosts file:

```
fred@bright82 ~]$ mpirun -np 2 -hostfile mpirun.hosts ./hybridhello
Hello I am Processor 0 on node001 of 2
Hello I am Processor 1 on node002 of 2
Hybrid Hello World: I am thread # 0 out of 3
Hybrid Hello World: I am thread # 2 out of 3
Hybrid Hello World: I am thread # 1 out of 3
Hybrid Hello World: I am thread # 0 out of 3
Hybrid Hello World: I am thread # 2 out of 3
Hybrid Hello World: I am thread # 1 out of 3
```

Benefits And Drawbacks Of Using OpenMP

The main benefit to using OpenMP is that it can decrease memory requirements, with usually no reduction in performance. Other benefits include:

- Potential additional parallelization opportunities besides those exploited by MPI.
- Less domain decomposition, which can help with load balancing as well as allowing for larger messages and fewer tasks participating in MPI collective operations.
- OpenMP is a standard, so any modifications introduced into an application are portable and appear as comments on systems not using OpenMP.
- By adding annotations to existing code and using a compiler option, it is possible to add OpenMP to a code somewhat incrementally, almost on a loop-by-loop basis. The vector loops in a code that vectorize well are good candidates for OpenMP.

There are also some potential drawbacks:

- OpenMP can be hard to program and/or debug in some cases.
- Effective usage can be complicated on NUMA systems due to locality considerations
- If an application is network- or memory- bandwidth-bound, then threading it is not going to help. In this case it will be OK to leave some cores idle.
- In some cases a serial portion may be essential, which can inhibit performance.
- In most MPI codes, synchronization is implicit and happens when messages are sent and received. However, with OpenMP, much synchronization must be added to the code explicitly. The programmer must also explicitly determine which variables can be shared among threads and which ones cannot (parallel scoping). OpenMP codes that have errors introduced by incomplete or misplaced synchronization or improper scoping can be difficult to debug because the error can introduce race conditions which cause the error to happen only intermittently.

3.3.5 Support Thread Levels

MPI defines four “levels” of thread safety. The maximum thread support level is returned by the `MPI_Init_thread` call in the “provided” argument.

An environment variable `MPICH_MAX_THREAD_SAFETY` can be set to different values to increase the thread safety:

<code>MPICH_MAX_THREAD_SAFETY</code>	Supported Thread Level
not set	<code>MPI_THREAD_SINGLE</code>
single	<code>MPI_THREAD_SINGLE</code>
funneled	<code>MPI_THREAD_FUNNELED</code>
serialized	<code>MPI_THREAD_SERIALIZED</code>
multiple	<code>MPI_THREAD_MULTIPLE</code>

3.3.6 Further Recommendations

Users face various challenges with running and scaling large scale jobs on peta-scale production systems. For example: certain applications may not have enough memory per core, the default environment variables may need to be adjusted, or I/O may dominate run time.

Possible ways to deal with these are:

- Trying out various compilers and compiler flags, and finding out which options are best for particular applications.

- Changing the default MPI rank ordering. This is a simple, yet sometimes effective, runtime tuning option that requires no source code modification, recompilation or re-linking. The default MPI rank placement on the compute nodes is SMP style. However, other choices are round-robin, folded rank, and custom ranking.
- Using fewer cores per node is helpful when more memory per process than the default is needed. Having fewer processes to share the memory and interconnect bandwidth is also helpful in this case. For NUMA nodes, extra care must be taken.
- Hybrid MPI/OpenMP reduces the memory footprint. Overlapping communication with computation in hybrid MPI/OpenMP can be considered.
- Some applications may perform better when large memory pages are used.

4

Workload Management

4.1 What Is A Workload Manager?

A workload management system (also known as a queueing system, job scheduler or batch submission system) manages the available resources such as CPUs, GPUs, and memory for jobs submitted to the system by users.

Jobs are submitted by the users using *job scripts*. Job scripts are constructed by users and include requests for resources. How resources are allocated depends upon policies that the system administrator sets up for the workload manager.

4.2 Why Use A Workload Manager?

Workload managers are used so that users do not manually have to keep track of node usage in a cluster in order to plan efficient and fair use of cluster resources.

Users may still perhaps run jobs on the compute nodes outside of the workload manager, if that is administratively permitted. However, running jobs outside a workload manager tends to eventually lead to an abuse of the cluster resources as more people use the cluster, and thus inefficient use of available resources. It is therefore usually forbidden as a policy by the system administrator on production clusters.

4.3 How Does A Workload Manager Function?

A workload manager uses policies to ensure that the resources of a cluster are used efficiently, and must therefore track cluster resources and jobs. A workload manager is therefore generally able to:

- Monitor:
 - the node status (up, down, load average)
 - all available resources (available cores, memory on the nodes)
 - the jobs state (queued, on hold, deleted, done)
- Modify:
 - the status of jobs (freeze/hold the job, resume the job, delete the job)
 - the priority and execution order for jobs
 - the run status of a job. For example, by adding checkpoints to freeze a job.
 - (optional) how related tasks in a job are handled according to their resource requirements. For example, a job with two tasks may have a greater need for disk I/O resources for the first task, and a greater need for CPU resources during the second task.

Some workload managers can adapt to external triggers such as hardware failure, and send alerts or attempt automatic recovery.

4.4 Job Submission Process

Whenever a job is submitted, the workload management system checks on the resources requested by the job script. It assigns cores, accelerators, local disk space, and memory to the job, and sends the job to the nodes for computation. If the required number of cores or memory are not yet available, it queues the job until these resources become available. If the job requests resources that are always going to exceed those that can become available, then the job accordingly remains queued indefinitely.

The workload management system keeps track of the status of the job and returns the resources to the available pool when a job has finished (that is, been deleted, has crashed or successfully completed).

4.5 What Do Job Scripts Look Like?

A job script looks very much like an ordinary shell script, and certain commands and variables can be put in there that are needed for the job. The exact composition of a job script depends on the workload manager used, but normally includes:

- commands to load relevant modules or set environment variables
- directives for the workload manager to request resources, control the output, set email addresses for messages to go to
- an execution (job submission) line

When running a job script, the workload manager is normally responsible for generating a machine file based on the requested number of processor cores (np), as well as being responsible for the allocation any other requested resources.

The executable submission line in a job script is the line where the job is submitted to the workload manager. This can take various forms.

Example

For the Slurm workload manager, the line might look like:

```
srun --mpi=mpich1_p4 ./a.out
```

Example

For PBS Pro it may simply be:

```
mpirun ./a.out
```

Example

For SGE it may look like:

```
mpirun -np 4 -machinefile $TMP/machines ./a.out
```

4.6 Running Jobs On A Workload Manager

The details of running jobs through the following workload managers is discussed later on, for:

- Slurm (Chapter 5)
- SGE (Chapter 6)
- PBS Pro (Chapter 7)

4.7 Running Jobs In Cluster Extension Cloud Nodes Using `cmsub`

Extra computational power from cloud service providers such as the Amazon Elastic Compute Cloud (EC2) can be used by an appropriately configured cluster managed by Bright Cluster Manager.

If the head node is running outside a cloud services provider, and at least some of the compute nodes are in the cloud, then this “hybrid” cluster configuration is called a Cluster Extension cluster, with the compute nodes in the cloud being the cloud extension of the cluster.

For a Cluster Extension cluster, job scripts to a workload manager should be submitted using Bright Cluster Manager’s `cmsub` utility. The `cmsub` utility should be configured beforehand by the administrator (section 4.3 of the *Cloudbursting Manual*). The `cmsub` utility allows the job to be considered for running on the extension (the cloud nodes). Jobs that are to run on the local regular nodes (not in a cloud) are not dealt with by `cmsub`.

`cmsub` users must have the profile `cloudjob` assigned to them by the administrator.

In addition, the environment module (section 2.3) `cmsub` is typically configured by the system administrator to load by default on the head node. It must be loaded for the `cmsub` utility to work.

The default settings for `cmsub` are configured by the cluster administrator. By default, the storage provided by Amazon’s S3 has an expiry date of 30 days (section 4.3 of the *Cloudbursting Manual*). Users planning to that keep data in the cloud may wish to check with the administrator what the S3 expiry setting is for them, if they have not already been informed about it.

4.7.1 Options For `cmsub`

Flag Options For `cmsub`

The basic usage for `cmsub` is:

```
cmsub [options] script
```

Options details are given by the `-h|--help` option for `cmsub`.

Users that are used to running jobs as root should note that the root user cannot usefully run a job with `cmsub`.

The user can submit some cloud-related values as options to `cmsub` on the command line, followed by the job script.

Example

```
$ cat myscript1
#!/bin/sh
hostname

$ cmsub myscript1
Submitting job: myscript1(slurm-2) [slurm:2] ... OK
```

Job-directive Style `#CMSUB` Directives For `cmsub`

All `cmsub` command line options can also be specified in a job-directive style format in the job script itself, using the “`#CMSUB`” tag to indicate an option.

Example

```
$ cat myscript2
#!/bin/sh
#CMSUB --input-list=/home/user/myjob.in
#CMSUB --output-list=/home/user/myjob.out
#CMSUB --remote-output-list=/home/user/file-which-will-be-created
#CMSUB --input=/home/user/onemoreinput.dat
#CMSUB --input=/home/user/myexec
myexec
```

```
$ csub myscript2
Submitting job: myscript2(slurm-2) [slurm:2] ... OK
```

Workload Manager Job-directives And Workload Manager Flag Options For `csub`

Workload manager job specifications can also be passed on.

Workload manager batch job tags are tags associated with the workload manager, such as `#SBATCH` for slurm (Chapter 5), or `#PBS` for PBS Pro (Chapter 7). These tags can also be used by the user to specify flags to be sent to the workload manager when submitting the job via `csub`. This can be done by

- using the tag itself (e.g: `#SBATCH` for slurm, `#PBS` for PBS Pro ...) These can be used along with the `#CMSUB` tags.

Example

```
$ cat myscript3
#!/bin/sh
#SBATCH -p partition
hostname
$ csub myscript3
Submitting job: myscript3(slurm-3) [slurm:3] ... OK
```

- or by using the `csub` flag option `--extra-flags` to specify the flag associated with the tag.

Example

```
$ cat myscript4
#!/bin/sh
hostname

$ csub --extra-flags="-p partition" myscript4
Submitting job: myscript4(slurm-4) [slurm:4] ... OK
```

5

Slurm

Slurm is a workload management system developed originally at the Lawrence Livermore National Laboratory. Slurm used to stand for Simple Linux Utility for Resource Management. However Slurm has evolved since then, and its advanced state nowadays means that the acronym is obsolete.

Slurm has both a graphical interface and command line tools for submitting, monitoring, modifying and deleting jobs. It is normally used with *job scripts* to submit and execute jobs. Various settings can be put in the job script, such as number of processors, resource usage, and application specific variables.

The steps for running a job through Slurm are to:

- Create the script or executable that will be handled as a job
- Create a job script that sets the resources for the script/executable
- Submit the job script to the workload management system

The details of Slurm usage depends upon the MPI implementation used. The description in this chapter will cover using Slurm's Open MPI implementation, which is quite standard. Slurm documentation can be consulted (http://slurm.schedmd.com/mpi_guide.html) if the implementation the user is using is very different.

5.1 Loading Slurm Modules And Compiling The Executable

In section 3.3.3 an MPI "Hello, world!" executable that can run in parallel is created and run in parallel outside a workload manager.

The executable can be run in parallel using the Slurm workload manager. For this, the Slurm module should first be loaded by the user on top of the chosen MPI implementation, in this case Open MPI:

Example

```
[fred@bright82 ~]$ module list
Currently Loaded Modulefiles:
  1) gcc/6.3.0                3) shared
  2) openmpi/gcc/64/1.10.3
[fred@bright82 ~]$ module add slurm; module list
Currently Loaded Modulefiles:
  1) gcc/6.3.0                3) shared
  2) openmpi/gcc/64/1.10.3    4) slurm/17.02.2
```

The "hello world" executable from section 3.3.3 can then be compiled and run for one task outside the workload manager, on the local host, as:

```
mpicc hello.c -o hello
mpirun -np 1 hello
```

5.2 Running The Executable With `salloc`

Running it as a job managed by Slurm can be done interactively with the Slurm allocation command, `salloc`, as follows

```
[fred@bright82 ~]$ salloc mpirun hello
```

Slurm is more typically run as a batch job (section 5.3). However execution via `salloc` uses the same options, and it is more convenient as an introduction because of its interactive behavior.

In a default Bright Cluster Manager configuration, Slurm auto-detects the cores available and by default spreads the tasks across the cores that are part of the allocation request.

To change how Slurm spreads the executable across nodes is typically determined by the options in the following table:

Short Option	Long Option	Description
-N	--nodes=	Request this many nodes on the cluster. Use all cores on each node by default
-n	--ntasks=	Request this many tasks on the cluster. Defaults to 1 task per node.
-c	--cpus-per-task=	request this many CPUs per task. (not implemented by Open MPI yet)
(none)	--ntasks-per-node=	request this number of tasks per node.

The full options list and syntax for `salloc` can be viewed with “`man salloc`”.

The requirement of specified options to `salloc` must be met before the executable is allowed to run. So, for example, if `--nodes=4` and the cluster only has 3 nodes, then the executable does not run.

5.2.1 Node Allocation Examples

The following session illustrates and explains some node allocation options and issues for Slurm using a cluster with just 1 compute node and 4 CPU cores:

Default settings: The `hello` MPI executable with default settings of Slurm runs successfully over the first (and in this case, the only) node that it finds:

```
[fred@bright82 ~]$ salloc mpirun hello
salloc: Granted job allocation 572
Hello world from process 0 out of 4, host name node001
Hello world from process 1 out of 4, host name node001
Hello world from process 2 out of 4, host name node001
Hello world from process 3 out of 4, host name node001
salloc: Relinquishing job allocation 572
```

The preceding output also displays if `-N1` (indicating 1 node) is specified, or if `-n4` (indicating 4 tasks) is specified.

The node and task allocation is almost certainly not going to be done by relying on defaults. Instead, node specifications are supplied to Slurm along with the executable.

To understand Slurm node specifications, the following cases consider and explain where the node specification is valid and invalid.

Number of nodes requested: The value assigned to the `-N|--nodes=` option is the number of nodes from the cluster that is requested for allocation for the executable. In the current cluster example it can only be 1. For a cluster with, for example, 1000 nodes, it could be a number up to 1000.

A resource allocation request for 2 nodes with the `--nodes` option causes an error on the current 1-node cluster example:

```
[fred@bright82 ~]$ salloc -N2 mpirun hello
salloc: error: Failed to allocate resources: Node count specification invalid
salloc: Relinquishing job allocation 573
```

Number of tasks requested per cluster: The value assigned to the `-n|--ntasks` option is the number of tasks that are requested for allocation from the cluster for the executable. In the current cluster example, it can be 1 to 4 tasks. The default resources available on a cluster are the number of available processor cores.

A resource allocation request for 5 tasks with the `--ntasks` option causes an error because it exceeds the default resources available on the 4-core cluster:

```
[fred@bright82 ~]$ salloc -n5 mpirun hello
salloc: error: Failed to allocate resources: More processors requested than permitted
```

Adding and configuring just one more node to the current cluster would allow the resource allocation to succeed, since an added node would provide at least one more processor to the cluster.

Number of tasks requested per node: The value assigned to the `--ntasks-per-node` option is the number of tasks that are requested for allocation from each node on the cluster. In the current cluster example, it can be 1 to 4 tasks. A resource allocation request for 5 tasks per node with `--ntasks-per-node` fails on this 4-core cluster, giving an output like:

```
[fred@bright82 ~]$ salloc --ntasks-per-node=5 mpirun hello
salloc: error: Failed to allocate resources: More processors requested than permitted
```

Adding and configuring another 4-core node to the current cluster would still not allow resource allocation to succeed, because the request is for at least 5 cores per node, rather than per cluster.

Restricting the number of tasks that can run per node: A resource allocation request for 2 tasks per node with the `--ntasks-per-node` option, and simultaneously an allocation request for 1 task to run on the cluster using the `--ntasks` option, runs successfully, although it uselessly ties up resources for 1 task per node:

```
[fred@bright82 ~]$ salloc --ntasks-per-node=2 --ntasks=1 mpirun hello
salloc: Granted job allocation 574
Hello world from process 0 out of 1, host name node005
salloc: Relinquishing job allocation 574
```

The other way round, that is, a resource allocation request for 1 task per node with the `--ntasks-per-node` option, and simultaneously an allocation request for 2 tasks to run on the cluster using the `--ntasks` option, fails because on the 1-cluster node, only 1 task can be allocated resources on the single node, while resources for 2 tasks are being asked for on the cluster:

```
[fred@bright82 ~]$ salloc --ntasks-per-node=1 --ntasks=3 mpirun hello
salloc: error: Failed to allocate resources: Requested node configuration is not available
salloc: Job allocation 575 has been revoked.
```

5.3 Running The Executable As A Slurm Job Script

Instead of using options appended to the `salloc` command line as in section 5.2, it is usually more convenient to send jobs to Slurm with the `sbatch` command acting on a job script.

A job script is also sometimes called a batch file. In a job script, the user can add and adjust the Slurm options, which are the same as the `salloc` options of section 5.2. The various settings and variables that go with the application can also be adjusted.

5.3.1 Slurm Job Script Structure

A job script submission for the Slurm batch job script format is illustrated by the following:

```
[fred@bright82 ~]$ cat slurmhello.sh
#!/bin/sh
#SBATCH -o my.stdout
#SBATCH --time=30      #time limit to batch job
#SBATCH -N 4
#SBATCH --ntasks=16
#SBATCH --ntasks-per-node=4
module add shared openmpi/gcc/64/1.10.3 slurm
mpirun hello
```

The structure is:

shebang line: shell definition line.

SBATCH lines: optional job script *directives* (section 5.3.2).

shell commands: optional shell commands, such as loading necessary modules.

application execution line: execution of the MPI application using `sbatch`, the Slurm submission wrapper.

In SBATCH lines, “`#SBATCH`” is used to submit options. The various meanings of lines starting with “`#`” are:

Line Starts With	Treated As
#	Comment in shell and Slurm
#SBATCH	Comment in shell, option in Slurm
# SBATCH	Comment in shell and Slurm

After the Slurm job script is run with the `sbatch` command (Section 5.3.4), the output goes into file `my.stdout`, as specified by the “`-o`” command.

If the output file is not specified, then the file takes a name of the form “`slurm-<jobnumber>.out`”, where `<jobnumber>` is a number starting from 1.

The command “`sbatch --usage`” lists possible options that can be used on the command line or in the job script. Command line values override script-provided values.

5.3.2 Slurm Job Script Options

Options, sometimes called “directives”, can be set in the job script file using this line format for each option:


```
#SBATCH {option} {parameter}
```

Directives are used to specify the resource allocation for a job so that Slurm can manage the job optimally. Available options and their descriptions can be seen with the output of `sbatch --help`. The more overviewable usage output from `sbatch --usage` may also be helpful.

Some of the more useful ones are listed in the following table:

Directive Description	Specified As
Name the job <i><jobname></i>	#SBATCH -J <i><jobname></i>
Request at least <i><minnodes></i> nodes	#SBATCH -N <i><minnodes></i>
Request <i><minnodes></i> to <i><maxnodes></i> nodes	#SBATCH -N <i><minnodes></i> - <i><maxnodes></i>
Request at least <i><MB></i> amount of temporary disk space	#SBATCH --tmp <i><MB></i>
Run the job for a time of <i><walltime></i>	#SBATCH -t <i><walltime></i>
Run the job at <i><time></i>	#SBATCH --begin <i><time></i>
Set the working directory to <i><directorypath></i>	#SBATCH -D <i><directorypath></i>
Set error log name to <i><jobname.err>*</i>	#SBATCH -e <i><jobname.err></i>
Set output log name to <i><jobname.log>*</i>	#SBATCH -o <i><jobname.log></i>
Mail <i><user@address></i>	#SBATCH --mail-user <i><user@address></i>
Mail on any event	#SBATCH --mail-type=ALL
Mail on job end	#SBATCH --mail-type=END
Run job in partition	#SBATCH -p <i><destination></i>
Run job using GPU with ID <i><number></i> , as described in section 8.5.2	#SBATCH --gres=gpu: <i><number></i>

*By default, both standard output and standard error go to a file:

```
slurm-<%j>.out
```

where *<%j>* is the job number.

5.3.3 Slurm Environment Variables

Available environment variables include:

SLURM_CPUS_ON_NODE - processors available to the job on this node

SLURM_JOB_ID - job ID of executing job

SLURM_LAUNCH_NODE_IPADDR - IP address of node where job launched

SLURM_NNODES - total number of nodes

SLURM_NODEID - relative node ID of current node

SLURM_NODELIST - list of nodes allocated to job

SLURM_NTASKS - total number of processes in current job

SLURM_PROCID - MPI rank (or relative process ID) of the current process

SLURM_SUBMIT_DIR - directory from which job was launched

SLURM_TASK_PID - process ID of task started

SLURM_TASKS_PER_NODE - number of tasks to be run on each node.

CUDA_VISIBLE_DEVICES - which GPUs are available for use

Typically, end users use SLURM_PROCID in a program so that an input of a parallel calculation depends on it. The calculation is thus spread across processors according to the assigned SLURM_PROCID, so that each processor handles the parallel part of the calculation with different values.

More information on environment variables is also to be found in the man page for `sbatch`.

5.3.4 Submitting The Slurm Job Script

Submitting a Slurm job script created like in the previous section is done by executing the job script with `sbatch`:

```
[fred@bright82 ~]$ sbatch slurmhello.sh
Submitted batch job 703
[fred@bright82 ~]$ cat slurm-703.out
Hello world from process 001 out of 004, processor name node001
...
```

Queues in Slurm terminology are called “partitions”. Slurm has a default queue called `defq`. The administrator may have removed this or created others.

If a particular queue is to be used, this is typically set in the job script using the `-p` or `--partition` option:

```
#SBATCH --partition=bitcoinsq
```

It can also be specified as an option to the `sbatch` command during submission to Slurm.

5.3.5 Checking And Changing Queued Job Status

After a job has gone into a queue, the queue status can be checked using the `squeue` command. The job number can be specified with the `-j` option to avoid seeing other jobs. The man page for `squeue` covers other options.

Jobs can be canceled with “`scancel <job number>`”.

The `scontrol` command allows users to see and change the job directives while the job is still queued. For example, a user may have specified a job, using the `--begin` directive, to start at 10am the next day by mistake. To change the job to start at 10pm tonight, something like the following session may take place:

```
[fred@bright82 ~]$ scontrol show jobid=254 | grep Time
RunTime=00:00:04 TimeLimit=UNLIMITED TimeMin=N/A
SubmitTime=2011-10-18T17:41:34 EligibleTime=2011-10-19T10:00:00
StartTime=2011-10-18T17:44:15 EndTime=Unknown
SuspendTime=None SecsPreSuspend=0
```

The parameter that should be changed is “`EligibleTime`”, which can be done as follows:

```
[fred@bright82 ~]$ scontrol update jobid=254 EligibleTime=2011-10-18T22:00:00
```

An approximate GUI Slurm equivalent to `scontrol` is the `sview` tool. This allows the job to be viewed under its jobs tab, and the job to be edited with a right click menu item. It can also carry out many other functions, including canceling a job.

Webbrowser-accessible job viewing is possible from the workload tab of the User Portal (section 12.2).

6

SGE

Sun Grid Engine (SGE) is a workload management and job scheduling system first developed to manage computing resources by Sun Microsystems. SGE has both a graphical interface and command line tools for submitting, monitoring, modifying and deleting jobs.

SGE uses *job scripts* to submit and execute jobs. Various settings can be put in the job script, such as number of processors, resource usage and application specific variables.

The steps for running a job through SGE are to:

- Create a job script
- Select the directives to use
- Add the scripts and applications and runtime parameters
- Submit it to the workload management system

6.1 Writing A Job Script

A binary cannot be submitted directly to SGE—a job script is needed for that. A job script can contain various settings and variables to go with the application. A job script format looks like:

```
#!/bin/bash
#$ Script options # Optional script directives
shell commands   # Optional shell commands
application       # Application itself
```

6.1.1 Directives

It is possible to specify options ('directives') to SGE by using '\$#' in the script. The difference in the meaning of lines that start with the '#' character in the job script file should be noted:

Line Starts With	Treated As
#	Comment in shell and SGE
#\$	Comment in shell, directive in SGE
# \$	Comment in shell and SGE

6.1.2 SGE Environment Variables

Available environment variables:

\$HOME - Home directory on execution machine
 \$USER - User ID of job owner
 \$JOB_ID - Current job ID
 \$JOB_NAME - Current job name; (like the -N option in qsub, qsh, qrsh, q\login and qalter)
 \$HOSTNAME - Name of the execution host
 \$TASK_ID - Array job task index number

6.1.3 Job Script Options

Options can be set in the job script file using this line format for each option:

```
#$ {option} {parameter}
```

Available options and their descriptions can be seen with the output of `qsub -help`:

Table 6.1.3: SGE Job Script Options

Option and parameter	Description
-a date_time	request a start time
-ac context_list	add context variables
-ar ar_id	bind job to advance reservation
-A account_string	account string in accounting record
-b y[es] n[o]	handle command as binary
-binding [env pe set] exp lin str	binds job to processor cores
-c ckpt_selector	define type of checkpointing for job
-ckpt ckpt-name	request checkpoint method
-clear	skip previous definitions for job
-cwd	use current working directory
-C directive_prefix	define command prefix for job script
-dc simple_context_list	delete context variable(s)
-dl date_time	request a deadline initiation time
-e path_list	specify standard error stream path(s)
-h	place user hold on job
-hard	consider following requests "hard"
-help	print this help
-hold_jid job_identifier_list	define jobnet interdependencies
-hold_jid_ad job_identifier_list	define jobnet array interdependencies
-i file_list	specify standard input stream file(s)
-j y[es] n[o]	merge stdout and stderr stream of job
-js job_share	share tree or functional job share
-jsv jsv_url	job submission verification script to be used
-l resource_list	request the given resources
-m mail_options	define mail notification events
-masterq wc_queue_list	bind master task to queue(s)

...continued

Table 6.1.3: SGE Job Script Options...continued

Option and parameter	Description
-notify	notify job before killing/suspending it
-now y[es] n[o]	start job immediately or not at all
-M mail_list	notify these e-mail addresses
-N name	specify job name
-o path_list	specify standard output stream path(s)
-P project_name	set job's project
-p priority	define job's relative priority
-pe pe-name slot_range	request slot range for parallel jobs
-q wc_queue_list	bind job to queue(s)
-R y[es] n[o]	reservation desired
-r y[es] n[o]	define job as (not) restartable
-sc context_list	set job context (replaces old context)
-shell y[es] n[o]	start command with or without wrapping <loginshell> -c
-soft	consider following requests as soft
-sync y[es] n[o]	wait for job to end and return exit code
-S path_list	command interpreter to be used
-t task_id_range	create a job-array with these tasks
-tc max_running_tasks	throttle the number of concurrent tasks (experimental)
-terse	tersed output, print only the job-id
-v variable_list	export these environment variables
-verify	do not submit just verify
-V	export all environment variables
-w e w n v p	verify mode (error warning none just verify poke) for jobs
-wd working_directory	use working_directory
-@ file	read commandline input from file

More detail on these options and their use is found in the man page for qsub.

6.1.4 The Executable Line

In a job script, the executable line is launched with the job launcher command after the directives lines have been dealt with, and after any other shell commands have been carried out to set up the execution environment.

Using mpirun In The Executable Line

The mpirun job-launcher command is used for executables compiled with MPI libraries. Executables that have not been compiled with MPI libraries, or which are launched without any specified number of nodes, run on a single free node chosen by the workload manager.

The executable line to run a program myprog that has been compiled with MPI libraries is run by placing the job-launcher command mpirun before it as follows:

```
mpirun myprog
```

Using cm-launcher With mpirun In The Executable Line

For SGE, for some MPI implementations, jobs sometimes leave processes behind after they have ended. A default Bright Cluster Manager installation provides a cleanup utility that removes such processes.

To use it, the user simply runs the executable line using the `cm-launcher` wrapper before the `mpirun` job-launcher command:

```
cm-launcher mpirun myprog
```

The wrapper tracks processes that the workload manager launches. When it sees processes that the workload manager is unable to clean up after a job is over, it carries out the cleanup instead. Using `cm-launcher` is recommended if jobs that do not get cleaned up correctly are an issue for the user or administrator.

6.1.5 Job Script Examples

Some job script examples are given in this section. Each job script can use a number of variables and directives.

Single Node Example Script

An example script for SGE:

```
noob@sgecluster:~$ cat application
#!/bin/sh
#$ -N sleep
#$ -S /bin/sh
# Make sure that the .e and .o file arrive in the
# working directory
#$ -cwd
#Merge the standard out and standard error to one file
#$ -j y
sleep 60
echo Now it is: `date`
```

Parallel Example Script

For parallel jobs the `-pe` (parallel environment) option must be assigned to the script. Depending on the interconnect, there may be a choice between a number of parallel environments such as MPICH (Ethernet) or MVAPICH (InfiniBand).

```
#!/bin/sh
#
# Your job name
#$ -N My_Job
#
# Use current working directory
#$ -cwd
#
# Join stdout and stderr
#$ -j y
#
# pe (Parallel environment) request. Set your number of requested slots here.
#$ -pe mpich 2
#
# Run job through bash shell
#$ -S /bin/bash

# If modules are needed, source modules environment:
. /etc/profile.d/modules.sh

# Add any modules you might require:
```

```

module add shared mpich/ge/gcc/64/3.1

# The following output will show in the output file. Used for debugging.

echo "Got $NSLOTS processors."
echo "Machines:"
cat machines

# Use MPIRUN to run the application
mpirun -machinefile machines ./application

```

The number of available slots can be set by the administrator to an arbitrary value. However, it is typically set so that it matches the number of cores in the cluster, for efficiency reasons. More slots can be set than cores, but most administrators prefer not to do that.

In a job script, the user can request slots from the available slots. Requesting multiple slots therefore typically means requesting multiple cores. In the case of an environment that is not set up as a parallel environment, the request for slots is done with the `-np` option. For jobs that run in a parallel environment, the `-pe` option is used. Mixed jobs, running in both non-MPI and parallel environments are also possible if the administrator has allowed it in the complex attribute slots settings.

Whether the request is granted is decided by the workload manager policy set by the administrator. If the request exceeds the number of available slots, then the request is not granted.

If the administrator has configured the cluster to use cloud computing with `cm-scale` (Chapter 8 of the *Administrator Manual*), then the total number of slots available to a cluster changes over time automatically, as nodes are started up and stopped dynamically.

6.2 Submitting A Job

The SGE module must be loaded first so that SGE commands can be accessed:

```
$ module add shared sge
```

With SGE a job can be submitted with `qsub`. The `qsub` command has the following syntax:

```
qsub [ options ] [ jobscript | -- [ jobscript args ] ]
```

After completion (either successful or not), output is put in the user's current directory, appended with the job number which is assigned by SGE. By default, there is an error and an output file.

```

myapp.e#{JOBID}
myapp.o#{JOBID}

```

6.2.1 Submitting To A Specific Queue

Some clusters have specific queues for jobs which run are configured to house a certain type of job: long and short duration jobs, high resource jobs, or a queue for a specific type of node.

To see which queues are available on the cluster the `qstat` command can be used:

```

qstat -g c

```

CLUSTER	QUEUE	CQLOAD	USED	RES	AVAIL	TOTAL	aoACDS	cdsuE
long.q		0.01	0	0	144	288	0	144
default.q		0.01	0	0	144	288	0	144

The job is then submitted, for example to the `long.q` queue:

```
qsub -q long.q sleeper.sh
```

6.2.2 Queue Assignment Required For `cm-scale`

If `cm-scale` is used with SGE, then jobs must be assigned to a queue by default, or `cm-scale` ignores the job. If the cluster administrator has not configured SGE to assign a queue to jobs by default, then the user can assign a queue to the job with the `-q` option in order to have `cm-scale` consider the job.

6.3 Monitoring A Job

The job status can be viewed with `qstat`. In this example the `sleeper.sh` script has been submitted. Using `qstat` without options will only display a list of jobs, with no queue status options:

```
$ qstat
job-ID  prior   name       user   state   submit/start at     queue                          slots
-----
  249  0.00000 Sleeper1   root    qw      12/03/2008 07:29:00              1
  250  0.00000 Sleeper1   root    qw      12/03/2008 07:29:01              1
  251  0.00000 Sleeper1   root    qw      12/03/2008 07:29:02              1
  252  0.00000 Sleeper1   root    qw      12/03/2008 07:29:02              1
  253  0.00000 Sleeper1   root    qw      12/03/2008 07:29:03              1
```

More details are visible when using the `-f` (for full) option:

- The Queue type `qtype` can be Batch (B) or Interactive (I).
- The `used/tot` or `used/free` column is the count of used/free slots in the queue.
- The `states` column is the state of the queue.

```
$ qstat -f
queuenam                                qtype  used/tot.  load_avg  arch              states
-----
all.q@node001.cm.cluster                BI      0/16      -NA-      1x26-amd64        au
all.q@node002.cm.cluster                BI      0/16      -NA-      1x26-amd64        au

#####
PENDING JOBS - PENDING JOBS - PENDING JOBS - PENDING JOBS - PENDING JOBS
#####
  249  0.55500 Sleeper1   root      qw      12/03/2008 07:29:00      1
  250  0.55500 Sleeper1   root      qw      12/03/2008 07:29:01      1
```

Job state can be:

- d(letion)
- E(rror)
- h(old)
- r(unning)
- R(estarted)
- s(uspended)
- S(uspended)
- t(ransferring)
- T(hreshold)

- w(aiting)

The queue state can be:

- u(nknown) if the corresponding sge_execd cannot be contacted
- a(larm) - the load threshold is currently exceeded
- A(larm) - the suspend threshold is currently exceeded
- C(alendar suspended) - see calendar_conf
- s(uspended) - see qmod
- S(ubordinate)
- d(isabled) - see qmod
- D(isabled) - see calendar_conf
- E(rror) - sge_execd was unable to locate the sge_shepherd - use qmod to fix it.
- o(rphaned) - for queue instances

By default the qstat command shows only jobs belonging to the current user, i.e. the command is executed with the option -u \$user. To see jobs from other users too, the following format is used:

```
$ qstat -u ``*''
```

6.4 Deleting A Job

A job can be deleted in SGE with the following command

```
$ qdel <jobid>
```

The job-id is the number assigned by SGE when the job is submitted using qsub. Only jobs belonging to the logged-in user can be deleted. Using qdel will delete a user's job regardless of whether the job is running or in the queue.

PBS Variants: Torque And PBS Pro

Bright Cluster Manager works with Torque and PBS Pro, which are two forks of Portable Batch System (PBS). PBS was a workload management and job scheduling system first developed to manage computing resources at NASA in the 1990s.

Torque and PBS Pro can differ significantly in the output they present when using their GUI visual tools. However because of their historical legacy, their basic design structure and job submission methods from the command line remain very similar for the user. Both Torque and PBS Pro are therefore covered in this chapter. The possible Torque schedulers (Torque's built-in scheduler, Maui, or Moab) are also covered when discussing Torque.

Torque and PBS Pro both offer a graphical interface and command line tools for submitting, monitoring, modifying and deleting jobs.

For submission and execution of jobs, both workload managers use PBS "job scripts". The user puts values into a job script for the resources being requested, such as the number of processors, memory. Other values are also set for the runtime parameters and application-specific variables.

The steps for running a job through a PBS job script are:

- Creating an application to be run via the job script
- Creating the job script, adding directives, applications, runtime parameters, and application-specific variables to the script
- Submitting the script to the workload management system

This chapter covers the using the workload managers and job scripts with the PBS variants so that users can get a basic understanding of how they are used, and can get started with typical cluster usage.

In this chapter:

- section 7.1 covers the components of a job script and job script examples
- section 7.2.1 covers submitting, monitoring, and deleting a job with a job script

More depth on using these workload managers is to be found in the PBS Professional User Guide and in the online Torque documentation at <http://www.adaptivecomputing.com/resources/docs/>.

7.1 Components Of A Job Script

To use Torque or PBS Pro, a batch job script is created by the user. The job script is a shell script containing the set of commands that the user wants to run. It also contains the resource requirement directives and other specifications for the job. After preparation, the job script is submitted to the workload manager using the qsub command. The workload manager then tries to make the job run according to the job script specifications.

A job script can be resubmitted with different parameters (e.g. different sets of data or variables).

7.1.1 Sample Script Structure

A job script in PBS Pro or Torque has a structure illustrated by the following basic example:

Example

```
#!/bin/bash
#
#PBS -l walltime=1:00:00
#PBS -l nodes=4
#PBS -l mem=500mb
#PBS -j oe

cd ${HOME}/myprogs
mpirun myprog a b c
```

The first line is the standard “shebang” line used for scripts.

The lines that start with #PBS are PBS directive lines, described shortly in section 7.1.2.

The last two lines are an example of setting remaining options or configuration settings up for the script to run. In this case, a change to the directory myprogs is made, and then run the executable myprog with arguments a b c. The line that runs the program is called the executable line (section 7.1.3).

To run the executable file in the executable line in parallel, the job launcher mpirun is placed immediately before the executable file. The number of nodes the parallel job is to run on is assumed to have been specified in the PBS directives.

7.1.2 Directives

Job Script Directives And qsub Options

A job script typically has several configurable values called job script directives, set with job script directive lines. These are lines that start with a “#PBS”. Any directive lines beyond the first executable line are ignored.

The lines are comments as far as the shell is concerned because they start with a “#”. However, at the same time the lines are special commands when the job script is processed by the qsub command. The difference is illustrated by the following:

- The following shell comment is only a comment for a job script processed by qsub:

```
# PBS
```

- The following shell comment is also a job script directive when processed by qsub:

```
#PBS
```

Job script directive lines with the “#PBS ” part removed are the same as options applied to the qsub command, so a look at the man pages of qsub describes the possible directives and how they are used. If there is both a job script directive and a qsub command option set for the same item, the qsub option takes precedence.

Since the job script file is a shell script, the shell interpreter used can be changed to another shell interpreter by modifying the first line (the “#!” line) to the preferred shell. Any shell specified by the first line can also be overridden by using the “#PBS -S” directive to set the shell path.

Walltime Directive

The workload manager typically has default walltime limits per queue with a value limit set by the administrator. The user sets walltime limit by setting the “#PBS -l walltime” directive to a specific time. The time specified is the maximum time that the user expects the job should run for, and it allows the workload manager to work out an optimum time to run the job. The job can then run sooner than it would by default.

If the walltime limit is exceeded by a job, then the job is stopped, and an error message like the following is displayed:

```
=> PBS: job killed:  walltime <runningtime> exceeded limit <settime>
```

Here, <runningtime> indicates the time for which the job actually went on to run, while <settime> indicates the time that the user set as the walltime resource limit.

Resource List Directives

Resource list directives specify arguments to the -l directive of the job script, and allow users to specify values to use instead of the system defaults.

For example, in the sample script structure earlier, a job walltime of one hour and a memory space of at least 500MB are requested (the script requires the size of the space be spelled in lower case, so “500mb” is used).

If a requested resource list value exceeds what is available, the job is queued until resources become available.

For example, if nodes only have 2000MB to spare and 4000MB is requested, then the job is queued indefinitely, and it is up to the user to fix the problem.

Resource list directives also allow, for example, the number of nodes (-l nodes) and the virtual processor cores per nodes (-l ppn) to be specified. If no value is specified, the default is 1 core per node.

If 8 cores are wanted, and it does not matter how the cores are allocated (e.g. 8 per node or 1 on 8 nodes) the directive used in Torque is:

```
#PBS -l nodes=8
```

For PBS Pro v11 this also works, but is deprecated, and the form “#PBS -l select=8” is recommended instead.

Further examples of node resource specification are given in a table on page 38.

Job Directives: Job Name, Logs, And IDs

If the name of the job script file is jobname, then by default the output and error streams are logged to jobname.o<number> and jobname.e<number> respectively, where <number> indicates the associated job number. The default paths for the logs can be changed by using the -o and -e directives respectively, while the base name (jobname here) can be changed using the -N directive.

Often, a user may simply merge both logs together into one of the two streams using the -j directive. Thus, in the preceding example, “-j oe” merges the logs to the output log path, while “-j eo” would merge it to error log path.

The job ID is an identifier based on the job number and the FQDN of the login node. For a login node called bright52.cm.cluster, the job ID for a job number with the associated value <number> from earlier, would by default be <number>.bright52.cm.cluster, but it can also simply be abbreviated to <number>.

Job Queues

Sending a job to a particular job queue is sometimes appropriate. An administrator may have set queues up so that some queues are for very long term jobs, or some queues are for users that require GPUs. Submitting a job to a particular queue <destination> is done by using the directive “#PBS -q <destination>”.

Directives Summary

A summary of the job directives covered, with a few extras, are shown in the following table:

Directive Description	Specified As
Name the job <i><jobname></i>	#PBS -N <i><jobname></i>
Run the job for a time of <i><walltime></i>	#PBS -l <i><walltime></i>
Run the job at <i><time></i>	#PBS -a <i><time></i>
Set error log name to <i><jobname.err></i>	#PBS -e <i><jobname.err></i>
Set output log name to <i><jobname.log></i>	#PBS -o <i><jobname.log></i>
Join error messages to output log	#PBS -j eo
Join output messages to error log	#PBS -j oe
Mail to <i><user@address></i>	#PBS -M <i><user@address></i>
Mail on <i><event></i>	#PBS -m <i><event></i>
where <i><event></i> takes the	(a)bort
value of the letter in	(b)egin
the parentheses	(e)nd
	(n) do not send email
Queue is <i><destination></i>	#PBS -q <i><destination></i>
Login shell path is <i><shellpath></i>	#PBS -S <i><shellpath></i>

Resource List Directives Examples

Examples of how requests for resource list directives work are shown in the following table:

Resource Example Description	"#PBS -l" Specification
Request 500MB memory	mem=500mb
Set a maximum runtime of 3 hours 10 minutes and 30 seconds	walltime=03:10:30
8 nodes, anywhere on the cluster	nodes=8*
8 nodes, anywhere on the cluster	select=8**
2 nodes, 1 processor per node	nodes=2:ppn=1
3 nodes, 8 processors per node	nodes=3:ppn=8
5 nodes, 2 processors per node and 1 GPU per node	nodes=5:ppn=2:gpus=1*
5 nodes, 2 processors per node, and 1 GPU per node	select=5:ncpus=2:ngpus=1**
5 nodes, 2 processors per node, 3 virtual processors for MPI code	select=5:ncpus=2:mpiprocs=3**
5 nodes, 2 processors per node, using any GPU on the nodes	select=5:ncpus=2:ngpus=1**
5 nodes, 2 processors per node, using a GPU with ID 0 from nodes	select=5:ncpus=2:gpu_id=0**

*For Torque 2.5.5

**For PBS Pro 11

Some of the examples illustrate requests for GPU resource usage. GPUs and the CUDA utilities for NVIDIA are introduced in Chapter 8. In the Torque and PBS Pro workload managers, GPU usage is treated like the attributes of a resource which the cluster administrator will have pre-configured according to local requirements.

For further details on resource list directives, the Torque and PBS Pro user documentation should be consulted.

7.1.3 The Executable Line

In the job script structure (section 7.1.1), the executable line is launched with the job launcher command after the directives lines have been dealt with, and after any other shell commands have been carried out to set up the execution environment.

Using `mpirun` In The Executable Line

The `mpirun` command is used for executables compiled with MPI libraries. Executables that have not been compiled with MPI libraries, or which are launched without any specified number of nodes, run on a single free node chosen by the workload manager.

The executable line to run a program `myprog` that has been compiled with MPI libraries is run by placing the job-launcher command `mpirun` before it as follows:

```
mpirun myprog
```

Using `cm-launcher` With `mpirun` In The Executable Line

For Torque, for some MPI implementations, jobs sometimes leave processes behind after they have ended. A default Bright Cluster Manager installation provides a cleanup utility that removes such processes. To use it, the user simply runs the executable line using the `cm-launcher` wrapper before the `mpirun` job-launcher command:

```
cm-launcher mpirun myprog
```

The wrapper tracks processes that the workload manager launches. When it sees processes that the workload manager is unable to clean up after the job is over, it carries out the cleanup instead. Using `cm-launcher` is recommended if jobs that do not get cleaned up correctly are an issue for the user or administrator.

7.1.4 Example Batch Submission Scripts

Node Availability

The following job script tests which out of 4 nodes requested with “-l nodes” are made available to the job in the workload manager:

Example

```
#!/bin/bash
#PBS -l walltime=1:00
#PBS -l nodes=4
echo -n "I am on: "
hostname;

echo finding ssh-accessible nodes:
for node in $(cat ${PBS_NODEFILE}) ; do
    echo -n "running on: "
    /usr/bin/ssh $node hostname
done
```

The directive specifying `walltime` means the script runs at most for 1 minute. The `${PBS_NODEFILE}` array used by the script is created and appended with hosts by the queuing system. The script illustrates how the workload manager generates a `${PBS_NODEFILE}` array based on the requested number of nodes, and which can be used in a job script to spawn child processes. When the script is submitted, the output from the log will look like:

```
I am on: node001
finding ssh-accessible nodes:
running on: node001
```

```
running on: node002
running on: node003
running on: node004
```

This illustrates that the job starts up on a node, and that no more than the number of nodes that were asked for in the resource specification are provided.

The list of all nodes for a cluster can be found using the `pbsnodes` command (section 7.2.6).

Using InfiniBand

A sample PBS script for InfiniBand is:

```
#!/bin/bash
#!
#! Sample PBS file
#!
#! Name of job

#PBS -N MPI

#! Number of nodes (in this case 8 nodes with 4 CPUs each)
#! The total number of nodes passed to mpirun will be nodes*ppn
#! Second entry: Total amount of wall-clock time (true time).
#! 02:00:00 indicates 02 hours

#PBS -l nodes=8:ppn=4,walltime=02:00:00

#! Mail to user when job terminates or aborts
#PBS -m ae

# If modules are needed by the script, then source modules environment:
. /etc/profile.d/modules.sh

# Add any modules you might require:
module add shared mvapich/gcc torque maui pbspro

#! Full path to application + application name
application="<application>"

#! Run options for the application
options="<options>"

#! Work directory
workdir="<work dir>"

#####
### You should not have to change anything below this line ###
#####

#! change the working directory (default is home directory)

cd $workdir

echo Running on host $(hostname)
echo Time is $(date)
echo Directory is $(pwd)
echo PBS job ID is $PBS_JOBID
```



```
echo This job runs on the following machines:
echo $(cat $PBS_NODEFILE | uniq)

mpirun_command="mpirun $application $options"

#! Run the parallel MPI executable (nodes*ppn)
echo Running $mpirun_command
eval $mpirun_command
```

In the preceding script, no machine file is needed, since it is automatically built by the workload manager and passed on to the `mpirun` parallel job launcher utility. The job is given a unique ID and run in parallel on the nodes based on the resource specification.

7.1.5 Links To Other Resources About Job Scripts In Torque And PBS Pro

A number of useful links are:

- Torque examples:
<http://bmi.cchmc.org/resources/software/torque/examples>
- PBS Pro script files:
<http://www.ccs.tulane.edu/computing/pbs/pbs.phtml>

7.2 Submitting A Job

7.2.1 Preliminaries: Loading The Modules Environment

To submit a job to the workload management system, the user must ensure that the following environment modules are loaded:

- If using Torque with no external scheduler:

```
$ module add shared torque
```

- If using Torque with Maui:

```
$ module add shared torque maui
```

- If using Torque with Moab:

```
$ module add shared torque moab
```

- If using PBS Pro:

```
$ module add shared pbspro
```

Users can pre-load particular environment modules as their default using the “`module init*`” commands (section 2.3.3).

7.2.2 Using `qsub`

The command `qsub` is used to submit jobs to the workload manager system. The command returns a unique job identifier, which is used to query and control the job and to identify output. The usage format of `qsub` and some useful options are listed here:

USAGE: qsub [<options>] <job script>

Option	Hint	Description
-----	----	-----
-a	at	run the job at a certain time
-l	list	request certain resource(s)
-q	queue	job is run in this queue
-N	name	name of job
-S	shell	shell to run job under
-j	join	join output and error files

For example, a job script called `mpirun.job` with all the relevant directives set inside the script, may be submitted as follows:

Example

```
$ qsub mpirun.job
```

A job may be submitted to a specific queue `testq` as follows:

Example

```
$ qsub -q testq mpirun.job
```

The man page for `qsub` describes these and other options. The options correspond to PBS directives in job scripts (section 7.1.1). If a particular item is specified by a `qsub` option as well as by a PBS directive, then the `qsub` option takes precedence.

7.2.3 Job Output

By default, the output from the job script `<scriptname>` goes into the home directory of the user for Torque, or into the current working directory for PBS Pro.

By default, error output is written to `<scriptname>.e<jobid>` and the application output is written to `<scriptname>.o<jobid>`, where `<jobid>` is a unique number that the workload manager allocates. Specific output and error files can be set using the `-o` and `-e` options respectively. The error and output files can usefully be concatenated into one file with the `-j oe` or `-j eo` options. More details on this can be found in the `qsub` man page.

7.2.4 Monitoring A Job

To use the commands in this section, the appropriate workload manager module must be loaded. For example, for Torque, `torque` module needs to be loaded:

```
$ module add torque
```

qstat Basics

The main component is `qstat`, which has several options. In this example, the most frequently used options are discussed.

In PBS/Torque, the command “`qstat -an`” shows what jobs are currently submitted or running on the queuing system. An example output is:

```
[fred@bright52 ~]$ qstat -an
bright52.cm.cluster:
      User
Job ID  name Queue  Jobname SessID NDS TSK  Req'd Req'd Elap
      Memory Time  S Time
-----
78.bright52 fred shortq tjob    10476  1  1  555mb 00:01 R 00:00
79.bright52 fred shortq tjob      --  1  1  555mb 00:01 Q  --
```

The output shows the Job ID, the user who owns the job, the queue, the job name, the session ID for a running job, the number of nodes requested, the number of CPUs or tasks requested, the time requested (-l walltime), the job state (S) and the elapsed time. In this example, one job is seen to be running (R), and one is still queued (Q). The -n parameter causes nodes that are in use by a running job to display at the end of that line.

Possible job states are:

Job States	Description
C	Job is completed (regardless of success or failure)
E	Job is exiting after having run
H	Job is held
Q	job is queued, eligible to run or routed
R	job is running
S	job is suspend
T	job is being moved to new location
W	job is waiting for its execution time

The command “qstat -q” shows what queues are available. In the following example, there is one job running in the testq queue and 4 are queued.

```
$ qstat -q
```

```
server: master.cm.cluster
```

Queue	Memory	CPU	Time	Walltime	Node	Run	Que	Lm	State
testq	--	--		23:59:59	--	1	4	--	E R
default	--	--		23:59:59	--	0	0	--	E R
						1	4		

showq From Maui

If the Maui scheduler is running, and the Maui module loaded (module add maui), then Maui’s showq command displays a similar output. In this example, one dual-core node is available (1 node, 2 processors), one job is running and 3 are queued (in the Idle state).

```
$ showq
```

```
ACTIVE JOBS-----
```

JOBNAME	USERNAME	STATE	PROC	REMAINING	STARTTIME
45	cvsupport	Running	2	1:59:57	Tue Jul 14 12:46:20
1 Active Job					
		2 of	2 Processors	Active	(100.00%)
		1 of	1 Nodes	Active	(100.00%)

```
IDLE JOBS-----
```

JOBNAME	USERNAME	STATE	PROC	WCLIMIT	QUEUETIME
46	cvsupport	Idle	2	2:00:00	Tue Jul 14 12:46:20
47	cvsupport	Idle	2	2:00:00	Tue Jul 14 12:46:21
48	cvsupport	Idle	2	2:00:00	Tue Jul 14 12:46:22

```
3 Idle Jobs
```

BLOCKED JOBS-----

JOBNAME	USERNAME	STATE	PROC	WCLIMIT	QUEUETIME
---------	----------	-------	------	---------	-----------

Total Jobs: 4 Active Jobs: 1 Idle Jobs: 3 Blocked Jobs: 0

Viewing Job Details With qstat And checkjob

Job Details With qstat With `qstat -f` the full output of the job is displayed. The output shows what the jobname is, where the error and output files are stored, and various other settings and variables.

```
$ qstat -f
Job Id: 19.mascm4.cm.cluster
  Job_Name = TestJobPBS
  Job_Owner = cvsupport@mascm4.cm.cluster
  job_state = Q
  queue = testq
  server = mascm4.cm.cluster
  Checkpoint = u
  ctime = Tue Jul 14 12:35:31 2009
  Error_Path = mascm4.cm.cluster:/home/cvsupport/test-package/TestJobPBS
  .e19
  Hold_Types = n
  Join_Path = n
  Keep_Files = n
  Mail_Points = a
  mtime = Tue Jul 14 12:35:31 2009
  Output_Path = mascm4.cm.cluster:/home/cvsupport/test-package/TestJobPB
  S.o19
  Priority = 0
  qtime = Tue Jul 14 12:35:31 2009
  Rerunable = True
  Resource_List.nodect = 1
  Resource_List.nodes = 1:ppn=2
  Resource_List.walltime = 02:00:00
  Variable_List = PBS_O_HOME=/home/cvsupport,PBS_O_LANG=en_US.UTF-8,
  PBS_O_LOGNAME=cvsupport,
  PBS_O_PATH=/usr/kerberos/bin:/usr/local/bin:/bin:/usr/bin:/sbin:/usr/
  sbin:/home/cvsupport/bin:/cm/shared/apps/torque/2.3.5/bin:/cm/shar
  ed/apps/torque/2.3.5/sbin,PBS_O_MAIL=/var/spool/mail/cvsupport,
  PBS_O_SHELL=/bin/bash,PBS_SERVER=mascm4.cm.cluster,
  PBS_O_HOST=mascm4.cm.cluster,
  PBS_O_WORKDIR=/home/cvsupport/test-package,PBS_O_QUEUE=default
  etime = Tue Jul 14 12:35:31 2009
  submit_args = pbs.job -q default
```

Job Details With checkjob The `checkjob` command (only for Maui) is particularly useful for checking why a job has not yet executed. For a job that has an excessive memory requirement, the output looks something like:

```
[fred@bright52 ~]$ checkjob 65
```

```
checking job 65
```

```
State: Idle
```

```
Creds: user:fred group:fred class:shortq qos:DEFAULT
```

```

WallTime: 00:00:00 of 00:01:00
SubmitTime: Tue Sep 13 15:22:44
  (Time Queued Total: 2:53:41 Eligible: 2:53:41)

Total Tasks: 1

Req[0] TaskCount: 1 Partition: ALL
Network: [NONE] Memory >= 0 Disk >= 0 Swap >= 0
Opsys: [NONE] Arch: [NONE] Features: [NONE]
Dedicated Resources Per Task: PROCS: 1 MEM: 495M

IWD: [NONE] Executable: [NONE]
Bypass: 0 StartCount: 0
PartitionMask: [ALL]
Flags:          RESTARTABLE

PE: 1.01 StartPriority: 173
job cannot run in partition DEFAULT (idle procs do not meet requirement\
s : 0 of 1 procs found)
idle procs: 3 feasible procs: 0

Rejection Reasons: [CPU          : 3]

```

The -v option gives slightly more detail.

7.2.5 Deleting A Job

An already submitted job can be deleted using the qdel command:

```
$ qdel <jobid>
```

The job ID is printed to the terminal when the job is submitted. To get the job ID of a job if it has been forgotten, the following can be used:

```
$ qstat
```

or

```
$ showq
```

7.2.6 Monitoring Nodes In Torque And PBS Pro

The nodes that the workload manager knows about can be viewed using the pbsnodes command.

The following output is from a cluster made up of 2-core nodes, as indicated by the value of 2 for ncpu for Torque and PBS Pro. If the node is available to run scripts, then its state is free or time-shared. When a node is used exclusively (section 8.5.2) by one script, the state is job-exclusive.

For Torque the display resembles (some output elided):

```

[fred@bright52 ~]$ pbsnodes -a
node001.cm.cluster
  state = free
  np = 3
  ntype = cluster
  status = rectime=1317911358,varattr=,jobs=96...ncpus=2...
  gpus = 1

node002.cm.cluster
  state = free

```

```
np = 3
...
gpus = 1
...
```

For PBS Pro the display resembles (some output elided):

```
[fred@bright52 ~]$ pbsnodes -a
node001.cm.cluster
  Mom = node001.cm.cluster
  ntype = PBS
  state = free
  pcpus = 3
  resources_available.arch = linux
  resources_available.host = node001
  ...
  sharing = default_shared

node002.cm.cluster
  Mom = node002.cm.cluster
  ntype = PBS
  state = free
  ...

...
```

8

Using GPUs

GPUs (Graphics Processing Units) are chips that provide specialized parallel processing power. Originally, GPUs were designed to handle graphics processing as part of the video processor, but their ability to handle non-graphics tasks in a similar manner has become important for general computing. GPUs designed for general purpose computing task are commonly called General Purpose GPUs, or GPGPUs.

A GPU is suited for processing an algorithm that naturally breaks down into a process requiring many similar calculations running in parallel. GPUs cores are able to rapidly apply the instruction on multiple data points organized in a 2-D, and more recently, 3-D, image. The image is placed in a framebuffer. In the original chips, the data points held in the framebuffer were intended for output to a display, thereby accelerating image generation.

The similarity between multicore CPU chips and modern GPUs makes it at first sight attractive to use GPUs for general purpose computing. However, the instruction set on GPGPUs is used in a component called the *shader pipeline*. This is, as the name suggests, to do with a limited set of graphics operations, and so is by its nature rather limited. Using the instruction set for problems unrelated to shader pipeline manipulations requires that the problems being processed map over to a similar manipulation. This works best for algorithms that naturally break down into a process requiring an operation to be applied in the same way on many independent vertices and pixels. In practice, this means that 1-D vector operations are an order of magnitude less efficient on GPUs than operations on triangular matrices.

Modern GPGPU implementations have matured so that they can now sub-divide their resources between independent processes that work on independent data, and they provide programmer-friendlier ways of data transfer between the host and GPU memory.

Physically, one GPU is typically a built-in part of the motherboard of a node or a board in a node, and consists of several hundred processing cores. There are also dedicated standalone units, commonly called GPU Units, consisting of several GPUs in one chassis. Several of these can be assigned to particular nodes, typically via PCI-Express connections, to increase the density of parallelism even further.

Bright Cluster Manager has several tools that can be used to set up and program GPUs for general purpose computations.

8.1 Packages

A number of different GPU-related packages are included in Bright Cluster Manager. Versions supported are CUDA 8.0, 9.0, 9.1, 9.2, 10.0, and 10.1.

For version 9.0, the packages include:

- `cuda-driver`: Provides the GPU driver
- `cuda90-sdk`: CUDA software developer kit
- `cuda90-toolkit`: CUDA toolkit
- `cuda-dcgm`: CUDA Data Center GPU Manager

- `cuda-xorg`: NVIDIA CUDA X.org drivers (optional)

The version implementation depends on how the system administrator has configured CUDA.

8.2 Using CUDA

After installation of the packages, for general usage and compilation it is sufficient to load just the `CUDA<version>/toolkit` module, where `<version>` is a number, 80, 90, 91, 92, 10.0, or 10.1 indicating the version. Versions indicated by the numbers in the range 80-92 are actually versions 8.0 to 9.2.

```
module load cuda10.1/toolkit
```

Also available are several other modules related to CUDA:

- `cuda10.1/blas`: Provides paths and settings for the CUBLAS library.
- `cuda10.1/fft`: Provides paths and settings for the CUFFT library.

The toolkit comes with the necessary tools and the NVIDIA compiler wrapper to compile CUDA C code.

Extensive documentation on how to get started, the various tools, and how to use the CUDA suite is in the `$CUDA_INSTALL_PATH/doc` directory.

8.3 Using OpenCL

OpenCL functionality is provided with the `cuda<version>/toolkit` environment module.

Examples of OpenCL code can be found in the `$CUDA_SDK/OpenCL` directory.

8.4 Compiling Code

Both CUDA and OpenCL involve running code on different *platforms*:

- `host`: with one or more CPUs
- `device`: with one or more CUDA enabled GPUs

Accordingly, both the host and device manage their own memory space, and it is possible to copy data between them. The CUDA and OpenCL Best Practices Guides in the `doc` directory, provided by the CUDA toolkit package, have more information on how to handle both platforms and their limitations.

The `nvcc` command by default compiles code and links the objects for both the host system and the GPU. The `nvcc` command distinguishes between the two and it can hide the details from the developer. To compile the host code, `nvcc` will use `gcc` automatically.

```
nvcc [options] <inputfile>
```

A simple example to compile CUDA code to an executable is:

```
nvcc testcode.cu -o testcode
```

The most used options are:

- `-g` or `-debug <level>`: This generates debug-able code for the host
- `-G` or `-device-debug <level>`: This generates debug-able code for the GPU
- `-o` or `-output-file <file>`: This creates an executable with the name `<file>`
- `-arch=sm_13`: This can be enabled if the CUDA device supports compute capability 1.3, which includes double-precision

If double-precision floating-point is not supported or the flag is not set, warnings such as the following will come up:

```
warning : Double is not supported. Demoting to float
```

The `nvcc` documentation manual, “*The CUDA Compiler Driver NVCC*” has more information on compiler options.

The CUDA SDK has more programming examples and information accessible from the file `$CUDA_SDK/C/Samples.html`.

For OpenCL, code compilation can be done by linking against the OpenCL library:

```
gcc test.c -lOpenCL
g++ test.cpp -lOpenCL
nvcc test.c -lOpenCL
```

8.5 Available Tools

8.5.1 CUDA gdb

The CUDA debugger can be started using: `cuda-gdb`. Details of how to use it are available in the “*CUDA-GDB (NVIDIA CUDA Debugger)*” manual, in the `doc` directory. It is based on GDB, the GNU Project debugger, and requires the use of the “`-g`” or “`-G`” options compiling.

Example

```
nvcc -g -G testcode.cu -o testcode
```

8.5.2 nvidia-smi

The NVIDIA System Management Interface command, `nvidia-smi`, can be used to allow exclusive access to the GPU. This means only one application can run on a GPU. By default, a GPU will allow multiple running applications.

Syntax:

```
nvidia-smi [OPTION1 [ARG1]] [OPTION2 [ARG2]] ...
```

The steps for making a GPU exclusive:

- List GPUs
- Select a GPU
- Lock GPU to a compute mode
- After use, release the GPU

After setting the compute rule on the GPU, the first application which executes on the GPU will block out all others attempting to run. This application does not necessarily have to be the one started by the user that set the exclusivity lock on the GPU!

To list the GPUs, the `-L` argument can be used:

```
$ nvidia-smi -L
GPU 0: (05E710DE:068F10DE) Tesla T10 Processor (S/N: 706539258209)
GPU 1: (05E710DE:068F10DE) Tesla T10 Processor (S/N: 2486719292433)
```

To set the ruleset on the GPU:

```
$ nvidia-smi -i 0 -c 1
```

The ruleset may be one of the following:

- 0 - Default mode (multiple applications allowed on the GPU)
- 1 - Exclusive thread mode (only one compute context is allowed to run on the GPU, usable from one thread at a time)
- 2 - Prohibited mode (no compute contexts are allowed to run on the GPU)
- 3 - Exclusive process mode (only one compute context is allowed to run on the GPU, usable from multiple threads at a time)

To check the state of the GPU:

```
$ nvidia-smi -i 0 -q
COMPUTE mode rules for GPU 0: 1
```

In this example, GPU0 is locked, and there is a running application using GPU0. A second application attempting to run on this GPU will not be able to run on this GPU.

```
$ histogram --device=0
main.cpp(101) : cudaSafeCall() Runtime API error :
no CUDA-capable device is available.
```

After use, the GPU can be unlocked to allow multiple users:

```
nvidia-smi -i 0 -c 0
```

8.5.3 CUDA Utility Library

CUTIL is a simple utility library designed for use in the CUDA SDK samples. There are 2 parts for CUDA and OpenCL. The locations are:

- \$CUDA_SDK/C/lib
- \$CUDA_SDK/OpenCL/common/lib

Other applications may also refer to them, and the toolkit libraries have already been pre-configured accordingly. However, they need to be compiled prior to use. Depending on the cluster, this might have already have been done.

```
[fred@demo ~] cd
[fred@demo ~] cp -r $CUDA_SDK
[fred@demo ~] cd $(basename $CUDA_SDK); cd C
[fred@demo C] make
[fred@demo C] cd $(basename $CUDA_SDK); cd OpenCL
[fred@demo OpenCL] make
```

CUTIL provides functions for:

- parsing command line arguments
- read and writing binary files and PPM format images
- comparing data arrays (typically used for comparing GPU results with CPU results)
- timers
- macros for checking error codes
- checking for shared memory bank conflicts

8.5.4 CUDA “Hello world” Example

A hello world example code using CUDA is:

Example

```
/*
  CUDA example
  "Hello World" using shift13, a rot13-like function.
  Encoded on CPU, decoded on GPU.

  rot13 cycles between 26 normal alphabet characters.

  shift13 shifts 13 steps along the normal alphabet characters
  So it translates half the alphabet into non-alphabet characters

  shift13 is used because it is simpler than rot13 in c
  so we can focus on the point

  (c) Bright Computing
  Taras Shapovalov <taras.shapovalov@brightcomputing.com>
*/
#include <cuda.h>  \/* remove this line in CUDA 6 onwards *\
#include <cutil_inline.h> \/* remove this line in CUDA 6 onwards *\
#include <stdio.h>

// CUDA kernel definition: undo shift13
__global__ void helloWorld(char* str) {
    int idx = blockIdx.x * blockDim.x + threadIdx.x;
    str[idx] -= 13;
}

int main(int argc, char** argv )
{
    char s[] = "Hello World!";
    printf("String for encode/decode: %s\n", s);

    // CPU shift13
    int len = sizeof(s);
    for (int i = 0; i < len; i++) {
        s[i] += 13;
    }
    printf("String encoded on CPU as: %s\n", s);

    // Allocate memory on the CUDA device
    char *cuda_s;
    cudaMalloc((void*)&cuda_s, len);

    // Copy the string to the CUDA device
    cudaMemcpy(cuda_s, s, len, cudaMemcpyHostToDevice);

    // Set the grid and block sizes  (dim3 is a type)
    // and "Hello World!" is 12 characters, say 3x4
    dim3 dimGrid(3);
    dim3 dimBlock(4);
```

```

// Invoke the kernel to undo shift13 in GPU
helloWorld<<< dimGrid, dimBlock >>>(cuda_s);

// Retrieve the results from the CUDA device
cudaMemcpy(s, cuda_s, len, cudaMemcpyDeviceToHost);

// Free up the allocated memory on the CUDA device
cudaFree(cuda_s);

printf("String decoded on GPU as: %s\n", s);
return 0;
}

```

The preceding code example may be compiled and run on the GPUs of a node with a GPU with:

```

[fred@node001 ~]$ module load shared cuda90/toolkit/9.0.176
[fred@node001 ~]$ nvcc hello.cu -o hello
[fred@node001 ~]$ ./hello
String for encode/decode: Hello World!
String encoded on CPU as: Uryy|-d|yq.
...
String encoded on CPU as: Uryy|-d|yq.
...
String decoded on GPU as: Hello World!
[fred@node001 ~]$

```

The number of characters displayed in the encoded string appear less than expected because there are unprintable characters in the encoding due to the cipher used being not exactly rot13.

8.5.5 OpenACC

OpenACC (<http://www.openacc-standard.org>) is a new open parallel programming standard aiming at simplifying the programmability of heterogeneous CPU/GPU computing systems. OpenACC allows parallel programmers to provide *OpenACC directives* to the compiler, identifying which areas of code to accelerate. This frees the programmer from carrying out time-consuming modifications to the original code itself. By pointing out parallelism to the compiler, directives get the compiler to carry out the details of mapping the computation onto the accelerator.

Using OpenACC directives requires a compiler that supports the OpenACC standard.

In the following example, where π is calculated, adding the `#pragma` directive is sufficient for the compiler to produce code for the loop that can run on either the GPU or CPU:

Example

```

#include <stdio.h>
#define N 1000000

int main(void) {
    double pi = 0.0f; long i;
    #pragma acc parallel loop reduction(+:pi)
    for (i=0; i<N; i++) {
        double t= (double)((i+0.5)/N);
        pi +=4.0/(1.0+t*t);
    }
    printf("pi=%16.15f\n",pi/N);
    return 0;
}

```

9

Using Kubernetes

9.1 Introduction To Kubernetes Running Via Bright Cluster Manager

Kubernetes is a system software for managing containerized applications across multiple hosts in a cluster.

- A container is an extremely lightweight virtualized operating system that runs without the unneeded extra emulated hardware components of a regular virtualized operating system.
- A containerized application runs within a container, and it only accesses files, environment variables, and libraries within the container, unless volumes are mounted and used.
- A containerized application provides services to other software or users. Kubernetes thus manages containerized applications as a service, and is aware of the container states and resources used.

Kubernetes provides mechanisms for application deployment, scheduling, updating, maintenance, and scaling. It actively manages the containers to ensure that the state of the cluster continually matches the user's intentions.

This chapter describes how Kubernetes works with Bright Cluster Manager, which currently supports Kubernetes 1.12.6. For details on Kubernetes that are outside the scope of its use with Bright Cluster Manager, the official Kubernetes documentation at <https://kubernetes.io/docs/> can be consulted.

By default, in Bright Cluster Manager the user is given access to Docker containers only via Kubernetes. The administrator can however configure direct access if required. In this chapter, only Docker container access via Kubernetes is described.

The `kubectl` utility is normally used to communicate with Kubernetes, although using the API directly instead of using `kubectl` is also possible. The `kubectl` utility can be used to get information about Kubernetes runtime, creation and management of *resources*, as well for other tasks. Resources are items such as pods (<https://kubernetes.io/docs/user-guide/walkthrough/#pods>) and volumes (<https://kubernetes.io/docs/user-guide/walkthrough/#volumes>), that are consumed while containers are in use.

The official Kubernetes documentation has some introductory tutorials, in particular an interactive one at:

<https://kubernetes.io/docs/tutorials/kubernetes-basics/deploy-app/deploy-interactive/>

Familiarity with the concepts in those tutorials is recommended before continuing with the rest of this chapter.

9.2 Kubernetes Quickstarts

This section provides quickstart recipes on some common tasks for an end user using Kubernetes.

Requirements:

- A Kubernetes cluster on Bright Cluster Manager. The administrator should have set this up as described in section 9.3 of the *Administrator Manual*.
- a dedicated user on the Kubernetes cluster

The simplest way for a user to use a Bright-managed Kubernetes cluster is if the cluster administrator has configured it for use via the head node. A user can then simply connect to the Kubernetes cluster via an ssh connection to the head node, and then load the environment via `module load kubernetes`. The remainder of this section can then be skipped.

An alternative way for a user to use a Bright-managed Kubernetes cluster avoids going via the head node, and uses a local PC.

9.2.1 Quickstart: Accessing The Kubernetes Dashboard

The Kubernetes Dashboard is a web browser-based way to manage Kubernetes tasks.

Requirements:

- from the local PC it should be possible to access the Kubernetes Dashboard URL at:
`https://dashboard.<kubernetes cluster name>:30443`
- If that does not work, then the cluster administrator has probably modified the standard configuration, and should be consulted on how to access the Kubernetes Dashboard.
- If the Dashboard is accessible, then the user needs a token to authenticate with the Kubernetes Dashboard.

Obtaining And Using The Token

A user test was created according to the procedure in section 9.3.9 of the *Administrator Manual*. For the user test, a token can be obtained from the head node with the following procedure, using the namespace and username of the user:

Example

```
[test@bright82 ~]$ module load kubernetes
[test@bright82 ~]$ USERNAME=test
[test@bright82 ~]$ NS=default
[test@bright82 ~]$ SECRET_NAME=$(kubectl get serviceaccount -n $NS $USERNAME -o \
  jsonpath='{.secrets[0].name}')
[test@bright82 ~]$ kubectl get secret -n $NS $SECRET_NAME -o jsonpath='{.data.token}' \
  | base64 -d ; echo
eyJhbGciOiJIUzI1NiIsImtpZCI6IiJ9.eyJpc3MiOiJrdWJlcm5ldGVzL3NlcnZpY2VhY2NvdW50Iiwia3ViZXJuZXRlcy5pby9zZXJ2aWNlYWNjb3VudC9uYW1lc3BhY2UiOiJkZWZhdWx0Iiwia3ViZXJuZXRlcy5pby9zZXJ2aWNlYWNjb3VudC9zZWNyZXQubmFtZSI6InRlc3QtdG9rZW4tbmtqb2w1LCJrdWJlcm5ldGVzLmlvL3NlcnZpY2VhY2NvdW50L3NlcnZpY2UuYWVhY2VudC5uYW1lc3QtdGVzdCI6Imt1YmVybWV0ZXMuW8vc2VydmljZWZjY291bnQvc2VydmljZS1hY2NvdW50LnVpZCI6IjNhZWZlYmQzLTNiN2EtMTF0S1lnZmRmLWZhMTYzZTliYjg5OCIsInN1YiI6InN5c3RlbTpxZXJ2aW\
N1YWNjb3VudDpkZWZhdWx0OnRlc3QifQ.ASMrLTyU6pcAndOq2NK13FyfC_g7nzdUP7QdcSmwG3HXoI5PUd6rxM_7V\
9VbE07bVAI_zi1Yh7jFnZqj3TbLDf4EY0jKogz00SHBHYe6FLiDLHIWPBo15lZe6fawZA_wuMH2Y-Vgieb-_L92ZXXKi\
IROJRiK-pGANQJG0Bu5khQjIeQ_mPPRPPZBESRC8RwEuTEp4FzTZ8nBEq-qKMOx3UpwBTx60Uj03XhmEeGGFmWFUDrZ\
Lo0mhjV10Zs10q8QsJnL9AXzTbE0deHlGPqjIomlo33zFwRQ0DDz8gz1vBFYNc4pPjRLpsQcE6qeLkpEoLtgM0tpdiJ\
oiGL207giHQ
```

If the username and related namespace are not known to the user, then the cluster administrator should be asked to provide these.

The output of the base64 command is the decoded token. This can be pasted from the terminal into the web browser, at the place where the token is asked for (figure 9.1):




Figure 9.1: Kubernete User Dashboard Authentication, Using Token Copy-Paste From A Terminal

After a successful authentication, the Dashboard displayed should appear as in figure 9.2:




Figure 9.2: Kuberne User Dashboard After Authentication

The user can now deploy a task, using the default namespace already defined. The task can be submitted as a YAML file, via the Dashboard URL

```
https://dashboard.<kubernetes cluster name>:30443#!/deploy?namespace=default
```

The task could be the `pi-job.yml` job of section 9.2.3. The result— π to 4000 places—can be seen in the log associated with the jobs, accessible from the Dashboard URL

```
https://dashboard.<kubernetes cluster name>:30443#!/job?namespace=default
```

9.2.2 Quickstart: Using `kubectl` From A Local Machine

The advantage of connecting from a local PC is that there is no need to connect to the head node via SSH.

Requirements:

- the local PC should be able to access the Kubernetes API server at `https://dashboard.<kubernetes cluster name>:30443`. The URL that is actually used is set up by the cluster administrator, who should be contacted for details.
- The local PC should be Linux-based and run on an amd64 architecture.

Steps:

- On the PC, `kubectl` for Kubernetes 1.12.6 should be downloaded from the head node. It can be downloaded to a directory in the user path, such as `/usr/bin`

Example

```
$ rsync <username>@<headnode>:/cm/local/apps/kubernetes/current/bin/kubectl \
<directory in the user path>
```

- The user can make a `.kube` directory on the PC. The Kubernetes configuration for the user `<username>` can then be picked up from the head node `<headnode>`. This includes the keys and the certificates:

```
$ mkdir ~/.kube
$ rsync <username>@<headnode>:.kube/config-<cluster-name> ~/.kube/config
```

- `localhost` must be replaced with the fully qualified domain name of the Kubernetes cluster
- The user can check if `kubectl` is able to connect to the cluster by running the following commands:

Example

```
$ kubectl cluster-info
$ kubectl get nodes
$ kubectl get all
```

9.2.3 Quickstart: Submitting Batch Jobs With `kubectl`

A batch job can be created in Kubernetes. It is simply referred to as a “job”. It is basically made up of non-persistent pods that run a one-off task.

A simple job to calculate π can be created by building a `pi-job.yml` file with the following content:

Example

```
apiVersion: batch/v1
kind: Job
metadata:
  name: pi
spec:
  completions: 8
  parallelism: 1
  template:
    metadata:
      name: pi
    spec:
      containers:
      - name: pi
        image: perl
        command: ["perl", "-Mbignum=bpi", "-wle", "print bpi(4000)"]
        restartPolicy: Never
```

This carries out a Perl-based calculation of π to 4000 places. Running it from the command line in Bash directly could be done with:

Example

```
$ perl -Mbignum=bpi -wle "print bpi(4000)"
```

However, the idea here is to demonstrate Kubernetes batch jobs firing up and scaling pods for this task instead, which is described next:

If the administrator has allowed the user access via Kubernetes policies, and has made the user a Kubernetes user, then the job can be submitted with:

```
$ kubectl apply -f pi-job.yml
job "pi" created
```

If the job is horizontally scalable, then the number of replicas can be scaled with:

```
$ kubectl scale job/pi --replicas=4
job "pi" scaled
```

Information about the job can be obtained with (output truncated):

```
$ kubectl get job/pi
NAME      DESIRED  SUCCESSFUL  AGE
pi        8        8           6m
$ kubectl describe job/pi
Name:      pi
Namespace: default
...
```

The jobs can be followed with (output truncated):

```
$ kubectl get pods -aw
NAME      READY    STATUS      RESTARTS  AGE
pi-74gnd  0/1      Completed   0          6m
...
```

The logs of a pod can be viewed with:

```
$ kubectl logs -f <pod name>
```

An output is shown that starts with:

```
3.141592653589793238462643383279502884197169399375105820974...
```

Further information on the following job topics can be found at the associated links:

- job: <https://kubernetes.io/docs/concepts/workloads/controllers/jobs-run-to-completion/>
- job parallelism: <https://kubernetes.io/docs/tasks/job/parallel-processing-expansion/>

9.2.4 Quickstart: Persistent Storage For Kubernetes Using Ceph

Pods running on Kubernetes can use a distributed storage system such as Ceph for persistent data storage.

The following are assumed:

- a working Ceph cluster
- a Kubernetes StorageClass for Ceph RBD

A `redis-persistent-storage.yml` file can be created for the Persistent Volume Claim (PVC), with the following content:

Example

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: redis-persistent-storage
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 1Gi
  storageClassName: fast
apiVersion: extensions/v1beta1
kind: Deployment
metadata:
  name: redis-master
spec:
  replicas: 1
  template:
    metadata:
      labels:
        app: redis
        role: master
    spec:
      containers:
        - name: redis-master
          image: gcr.io/google_containers/redis:e2e
          args: [
            '/usr/local/bin/redis-server',
            '--appendonly', 'yes',
            '--appendfsync', 'always']
          resources:
            requests:
              cpu: 100m
              memory: 100Mi
          ports:
            - containerPort: 6379
          volumeMounts:
            - name: redis-storage
              mountPath: /data
      volumes:
        - name: redis-storage
          persistentVolumeClaim:
            claimName: redis-persistent-storage
```

The Redis master deployment with PVC can then be created on Ceph persistent storage using:

```
$ kubectl apply -f redis-persistent-storage.yml
deployment "redis-master" created
```

Data can now be stored on Redis. After storing data on Redis, if all the pods are then deleted, they can be recreated without any data loss.

9.2.5 Quickstart: Helm, The Kubernetes Package Manager

Helm <https://docs.helm.sh/> is a tool for managing *charts*. Charts are packages of pre-configured Kubernetes resources.

The Helm client and Tiller (Helm server) components are installed and properly configured by default as a Kubernetes add-on. They are initialized for every Kubernetes user when the Kubernetes module is loaded—there is no `helm init` or similar that needs to be carried out first. For example (some text elided):

Example

```
$ module load kubernetes
$ helm version
Client: &version.Version{SemVer:"v2.11.0", GitCommit:"2e55dbe...7b146b", GitTreeState:"clean"}
Server: &version.Version{SemVer:"v2.11.0", GitCommit:"2e55dbe...7b146b", GitTreeState:"clean"}
```

Choices can be made from among the charts at the official repository at <https://github.com/kubernetes/charts>. For example, GitLab and WordPress can be installed with:

```
$ helm install stable/gitlab --name my-gitlab
$ helm install stable/wordpress --name my-wordpress
```

A tutorial on using Helm is available at https://docs.helm.sh/using_helm/#using-helm

10

Spark On Kubernetes

Apache Spark is “a lightning-fast unified analytics engine for big data and machine learning”. It is run within Kubernetes in Bright Cluster Manager to run workloads.

Spark documentation is available at <https://spark.apache.org/docs/>, and for Spark version 2.4.1, running Spark on Kubernetes is described at <http://spark.apache.org/docs/2.4.1/running-on-kubernetes.html>.

Since Spark version 2.3, support for PySpark has been added, as well as *client mode* support. This means that Spark can be used interactively with Python jobs, for example, via a Jupyter Notebook.

10.0.1 Important Requirements

By default only the root user of the cluster can access Kubernetes. Since that is not very useful, the cluster administrator can grant access to regular users by using `cm-kubernetes-setup` with the `--add-user` flag.

The regular user should check that Kubernetes can be accessed via the user’s account, or Spark workloads will fail to run.

```
[test@cluster ~]$ module load kubernetes/default/1.12.6
[test@cluster ~]$ kubectl get all
```

NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
service/kubernetes	ClusterIP	10.150.0.1	<none>	443/TCP	8h

10.0.2 Using `spark-submit` To Submit A Job

The Spark documentation suggests a Pi run. The user `test` can carry out the run with:

```
[test@cluster ~]$ module load spark
[test@cluster ~]$ spark-submit \
  --master k8s://https://localhost:10443 \
  --deploy-mode cluster \
  --name spark-pi \
  --class org.apache.spark.examples.SparkPi \
  --conf spark.executor.instances=5 \
  --conf spark.kubernetes.container.image=\
docker.io/brightcomputing/spark:2.4.1 \
  --conf spark.kubernetes.authenticate.driver.serviceAccountName=spark \
  local:///opt/spark/examples/jars/spark-examples_2.11-2.4.1.jar
...
```

The `spark-submit` command produces verbose output, which has been omitted.

Accessing The Job Output While the job is running, and after it finishes, its output can be viewed using a query in the form: `kubectl logs <pod>`:

```
[test@cluster ~]$ kubectl get pod
NAME                                READY   STATUS    RESTARTS   AGE
spark-pi-1540839816788-driver      0/1     Completed 0           34s
[test@cluster ~]$ kubectl logs spark-pi-1540839816788-driver
...
Pi is roughly 3.140760
2018-10-29 19:18:03 INFO  AbstractConnector:318 - Stopped Spark@31104936{HTTP...
2018-10-29 19:18:03 INFO  SparkUI:54 - Stopped Spark web UI at http://spark-pi-...
```

Accessing The Spark User Interface The Spark User Interface (Spark UI) is shut down once the job has finished. For longer-running jobs it makes sense to access the Spark UI while the job is running.

The `kubectl port-forward` command can be used to allow access to the Spark UI:

```
[test@cluster ~]$ module load kubernetes
[test@cluster ~]$ kubectl get pod
NAME                                READY   STATUS    RESTARTS   AGE
spark-pi-1540840666830-driver      0/1     Completed 0           4m34s
spark-pi-1540840938874-driver      0/1     Running   0           2s
[test@cluster ~]$ kubectl port-forward spark-pi-1540840938874-driver 3000:4040
Forwarding from 127.0.0.1:3000 -> 4040
Forwarding from [::1]:3000 -> 4040
Handling connection for 3000
```

The preceding example makes the dashboard available via local port 3000 on the machine where the `port-forward` command is executed. The Spark UI runs on port 4040 inside the pod, and displays something like in figure 10.1:




Figure 10.1: The Spark dashboard, forwarded on port 3000

10.0.3 Submitting A Python Job With `spark-submit`

Instead of using the `docker.io/brightcomputing/spark:2.4.0-SNAPSHOT` Docker image, the `docker.io/brightcomputing/spark-py:2.4.0-SNAPSHOT` image should be used:

Example

```
[test@cluster ~]$ module load spark/2.4.0
[test@cluster ~]$ spark-submit \
--master k8s://https://localhost:10443 \
--deploy-mode cluster \
--name spark-pi \
--class org.apache.spark.examples.SparkPi \
--conf spark.kubernetes.namespace=default --conf spark.executor.instances=5 \
--conf spark.kubernetes.container.image=\
docker.io/brightcomputing/spark-py:2.4.0-SNAPSHOT \
--conf spark.kubernetes.authenticate.driver.serviceAccountName=spark \
local:///opt/spark/examples/src/python/pi.py
...
```

A list of all possible configuration parameters is available at: <https://spark.apache.org/docs/latest/running-on-kubernetes.html#spark-properties>.

10.0.4 Running A PySpark Notebook In JupyterHub

To run a PySpark notebook in JupyterHub in a user account, the example Jupyter Notebook should be copied to the home directory of the user:

```
[test@cluster ~]$ cp /cm/shared/apps/spark/current/examples/pyspark_on_k8s_example.ipynb .
```

Assuming the user has access to Kubernetes, JupyterHub can be logged into. The example file should be navigated to, and executed with the PySpark kernel.

This starts up some pods in Kubernetes. Pods can be listed by running `kubectl get pods`.

The pods keep running so long as the kernel keeps running. Once the kernel is terminated, the pods disappear.

The user can also force their termination by calling the `close` method on the Spark Context object (`sc`).

This is also demonstrated in the example Notebook (figure 10.2):




Figure 10.2: The example kernel being executed on JupyterHub

10.0.5 How To Build A Custom Docker Image

Custom Docker images can also be created by the user.

The first prerequisite is access to Docker on the cluster. The cluster administrator may need to add the user to the docker group with a command in the form: `usermod -aG docker <username>`. The user should then make sure that the docker module is loaded:

Example

```
[test@cluster ~]$ module load docker/17.03.2
[test@cluster ~]$ docker ps
CONTAINER ID        IMAGE                                     ...
753d20aa3913       quay.io/calico/cni@sha256:ae3352d2c5dc1631a82777b4f584655d78089...
1049a3d91e79       quay.io/calico/node@sha256:e546014887cd5663cdd199d3a84dfc355cfe...
d9d6297fe269       k8s.gcr.io/pause:3.1                  ...
```

Assuming that the cluster administrator has already deployed a Docker Registry on node001, accessible via port 5000, then the procedure is:

- The Spark directory is copied to the home directory of the user. This allows modifications to be done easily:
`cp -Lpr /cm/shared/apps/spark/current $HOME/spark`
- The working directory is changed to this directory:
`cd $HOME/spark`

The Dockerfiles are located underneath the kubernetes sub-directory. The user can examine them and modify them according to need.

- The following script should be run to build and push both Dockerfiles:

Example

```
./bin/docker-image-tool.sh -r node001:5000/brightcomputing -t v2.4.0-CUSTOM build
```

The build command produces a lot of output. It builds the regular spark image for submitting JAR files, and then the spark-py image for submitting Python jobs.

In between, it pushes the Docker images to the specified registry, which is at node001:5000/brightcomputing in the preceding example.

The original `docker-image-tool.sh` pushes via a separate command, `push` in the command line arguments, instead of `build`. However there is an issue with this approach, so `build` has been modified to implicitly push the Docker images out.

The reason for the change is that `spark-py` by default builds upon the `spark` image, so that if it is not pushed in-between, the build fails. When Apache Spark 2.4.0 is definitively released, it is expected that the `docker-image-tool.sh` is changed so that this workaround is no longer needed.

An example build session could look like:

```
[test@cluster ~]$ cd spark
[test@cluster spark]$ ./bin/docker-image-tool.sh -r node001:5000/brightcomputing -t v2.4.0-CUSTOM build
Sending build context to Docker daemon 218.1 MB
Step 1/13 : FROM openjdk:8-alpine
---> 97bc1352afde
Step 2/13 : ARG spark_jars=jars
---> Using cache
---> 30bf749caa83
Step 3/13 : ARG img_path=kubernetes/dockerfiles
---> Using cache
```



```

---> 8064e3b4d723
...
Sending build context to Docker daemon 218.1 MB
Step 1/8 : FROM node001:5000/brightcomputing/spark:v2.4.0-CUSTOM
---> 23db6e958329
Step 2/8 : WORKDIR /
---> 309d0be6fe6f
Removing intermediate container c37ed0be5b27
Step 3/8 : RUN mkdir ${SPARK_HOME}/python
---> Running in e496b0813423
---> 5425d33b3abb
...

```

When invoking the `spark-submit` command, as in the example in section 10.0.3, the user can use a custom-built container such as this.

Thus, in `spark-submit`, the custom-built image `node001:5000/brightcomputing/spark-py:v2.4.0-CUSTOM` can be set as the value for the `spark.kubernetes.container.image` parameter.

10.0.6 Mounting Volumes Into Containers

The official documentation at <https://spark.apache.org/docs/latest/running-on-kubernetes.html#using-kubernetes-volumes> gives an outline of how volumes can be mounted into containers.

In summary, there are 3 ways a Kubernetes volume (<https://kubernetes.io/docs/concepts/storage/volumes>) can be mounted:

1. `hostPath`: mounts a file or directory from the host node's filesystem into a pod.
2. `emptyDir`: an initially empty volume, created when a pod is assigned to a node.
3. `persistentVolumeClaim`: used to mount a `PersistentVolume` into a pod.

Mounting A `hostPath`

The official documentation mentions adding the following two flags to specify how the volume is mounted inside the container:

```

--conf spark.kubernetes.driver.volumes.[VolumeType].[VolumeName].mount.path=<mount path>
--conf spark.kubernetes.driver.volumes.[VolumeType].[VolumeName].mount.readOnly=<true|false>

```

The following flag should also be added, to specify the path on the host:

```

--conf spark.kubernetes.driver.volumes.[VolumeType].[VolumeName].options.path=<mount path>

```

The volumes can be specified for each *executor* as well as for the *driver*. For an executor, the specification should use `spark.kubernetes.executor` instead of `spark.kubernetes.driver`.

For example, the NFS share `/cm/shared` of a standard Bright Cluster Manager could be made available on executor pods by adding the following 3 flags to the `spark-submit` command:

Example

```

module load kubernetes/default
module load spark
spark-submit \
  --master k8s://https://localhost:10443 \
  --deploy-mode cluster \
  --name spark-pi \
  --class org.apache.spark.examples.SparkPi \
  --conf spark.kubernetes.namespace=default \
  --conf spark.executor.instances=2 \

```

```
--conf spark.kubernetes.container.image=docker.io/brightcomputing/spark:2.4.0 \
--conf spark.kubernetes.authenticate.driver.serviceAccountName=spark \
--conf spark.kubernetes.executor.volumes.hostPath.cmshared.options.path=/cm/shared \
--conf spark.kubernetes.executor.volumes.hostPath.cmshared.mount.path=/data \
--conf spark.kubernetes.executor.volumes.hostPath.cmshared.mount.readOnly=false \
local:///opt/spark/examples/jars/spark-examples_2.11-2.4.0.jar 10000
```

This results in /cm/shared being mounted in read-write mode on the mount path /data:

```
[root@cluster ~]# kubectl get pod
NAME                                READY   STATUS    RESTARTS   AGE
spark-pi-1552563523319-driver      0/1     Completed 0           23h
spark-pi-1552648768369-driver      0/1     Completed 0           5m40s
spark-pi-1552648961734-driver      0/1     Completed 0           2m26s
spark-pi-1552649048516-driver      1/1     Running   0           59s
spark-pi-1552649048516-exec-1     1/1     Running   0           53s
spark-pi-1552649048516-exec-2     1/1     Running   0           53s
[root@cluster ~]# kubectl exec -it spark-pi-1552649048516-exec-1 /bin/bash
bash-4.4# mount | grep shared
master:/cm/shared on /data type nfs (rw,relatime,vers=3,...)
bash-4.4# ls -l /data
total 12
drwxr-xr-x 39 root root      4096 Mar 13 10:11 apps
drwxr-xr-x 13 root root      162 Mar  3 21:22 docs
drwxr-xr-x  3 root root       43 Mar  3 21:22 examples
-rw-r--r--  1 root root      101 Mar 14 11:14 init.sh
drwxr-xr-x  3 root root       16 Mar  3 21:29 licenses
drwxr-xr-x 28 root root     4096 Mar 12 13:31 modulefiles
bash-4.4#
```

Using Persistent Volume Claims

Spark in this case assumes that the Kubernetes cluster being managed by the user has persistent volumes available. A list of persistent volumes types can be found at: <https://kubernetes.io/docs/concepts/storage/persistent-volumes/#types-of-persistent-volumes>.

Claims to specific types of storage can be created for use with Spark. If spark-submit tries to use a persistent volume claim, then it assumes the claim already exists. It does not initiate a claim by itself.

In the following specification, for demonstration purposes, a claim my-claim is created:

```
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  name: my-claim
spec:
  accessModes:
    - ReadWriteOnce
  resources:
    requests:
      storage: 1000Gi
```

This claim should bind to a persistent volume that meets the criteria. If none are configured, then the user can create a local volume for /cm/shared, for example with:

```
kind: PersistentVolume
apiVersion: v1
metadata:
  name: kube-pv-volume
```

```

labels:
  type: local
spec:
  capacity:
    storage: 1000Gi
  accessModes:
    - ReadWriteOnce
  hostPath:
    path: /cm/shared

```

Applying the above two YAML configurations should result in the persistent volume claim object `my-claim`, and the persistent volume `kube-pv-volume` in Kubernetes:

```

[root@cluster ~]# kubectl get pv
NAME             CAPACITY  ACCESS MODES  RECLAIM POLICY  STATUS  CLAIM             STORAGECLASS
kube-pv-volume   1000Gi    RWO           Retain          Bound   default/my-claim

```

```

[root@cluster ~]# kubectl get pvc
NAME      STATUS  VOLUME             CAPACITY  ACCESS MODES  STORAGECLASS  AGE
my-claim  Bound   kube-pv-volume     1000Gi    RWO           default/my-claim  5m35s

```

Example

Invoking `spark-submit` as follows will then try to find the claim with name `my-claim`.

```

module load kubernetes/default
module load spark
spark-submit \
  --master k8s://https://localhost:10443 \
  --deploy-mode cluster \
  --name spark-pi \
  --class org.apache.spark.examples.SparkPi \
  --conf spark.kubernetes.namespace=default \
  --conf spark.executor.instances=2 \
  --conf spark.kubernetes.container.image=docker.io/brightcomputing/spark:2.4.0 \
  --conf spark.kubernetes.authenticate.driver.serviceAccountName=spark \
  --conf \
  spark.kubernetes.executor.volumes.persistentVolumeClaim.cmshared.options.claimName=my-claim \
  --conf spark.kubernetes.executor.volumes.persistentVolumeClaim.cmshared.mount.path=/data \
  --conf spark.kubernetes.executor.volumes.persistentVolumeClaim.cmshared.mount.readOnly=false \
  local:///opt/spark/examples/jars/spark-examples_2.11-2.4.0.jar 10000

```

```

[root@cluster ~]# kubectl get pod
NAME                                READY  STATUS      RESTARTS  AGE
spark-pi-1552563523319-driver       0/1    Completed   0          24h
spark-pi-1552648768369-driver       0/1    Completed   0          22m
spark-pi-1552648961734-driver       0/1    Completed   0          18m
spark-pi-1552649048516-driver       0/1    Completed   0          17m
spark-pi-1552649606812-driver       0/1    Completed   0          8m9s
spark-pi-1552650084516-driver       1/1    Running     0          11s
spark-pi-1552650084516-exec-1      1/1    Running     0          4s
spark-pi-1552650084516-exec-2      1/1    Running     0          3s

```

The claim that was specified can be found in the pod description:

```

[root@cluster ~]# kubectl describe pod spark-pi-1552650084516-exec-1 | grep my-claim -C 2
cmshared:

```

```
Type:      PersistentVolumeClaim (reference to a PersistentVolumeClaim in the same namespace)
ClaimName: my-claim
ReadOnly:   false
default-token-rvrf8:
```

Inside the executor pods /data is then found to be available, and presents the contents of /cm/shared from the host OS.

11

Using Singularity

Singularity is a tool that allows applications to be packaged and run in containers. Singularity containers can include a simple binary and library stack, or a complicated work flow. The packaged applications are then called Singularity images. These images are completely portable, with their only dependency requirement being that Singularity must be running on the target system.

Bright Cluster Manager provides the `cm-singularity` package. This allows users to create container images, which are run in containers. The containers can also be used with MPI applications and with different workload managers. The containers run within user space and are always executed as the run-time user (non-root). The application within the container may have access to the filesystem inside or outside the container. The package also provides a modulefile called `singularity` that must be loaded before using the singularity command line utility or running a Singularity container.

In this chapter several examples are given of how to create container images and start Singularity containers.

11.1 How To Build A Simple Container Image

The Singularity image is a single file which physically contains the container filesystem. Singularity container images can be bootstrapped with a *definition file*. The definition file describes how the container is to be built. There are several Singularity keywords (parameters) in the definition file, laid out in lines. If a line does not contain a Singularity keyword, then the line is treated as a shell script line.

The main keywords in the definition file are:

- **BootStrap**: The name of the Linux distribution type module. This informs Singularity which distribution module should be used to parse the commands in the definition file. At present the following 4 modules are supported:
 - **yum**: Bootstraps distributions such as Red Hat, Centos, and Scientific Linux.
 - **debootstrap**: Bootstraps Debian- and Ubuntu-based distributions.
 - **arch**: Bootstraps Arch Linux.
 - **docker**: Bootstraps Docker. It creates a core operating system image based on an image hosted on a particular Docker Registry server. For the docker module, several other keywords may also be defined:
 - * **From**: this keyword defines the string of the registry name used for this image in the format `[name] : [version]`.
 - * **IncludeCmd**: use the Docker-defined Cmd as the `%runscript`, if the Cmd is defined,
 - * **From**: sets the docker registry name,
 - * **Token**: sets the docker authorization token.
- **MirrorURL**: the URL to get packages from.

- `OSVersion`: this keyword must be defined as the alphabet-character string associated with the version of the distribution you wish to use. For example: `trusty` or `stable`.
- `Include`: install additional packages.
- `%setup`: this section blob is a bash scriptlet that is executed on the host outside the container, during bootstrapping.
- `%post`: this scriptlet section is executed once from inside the container, during bootstrapping.
- `%runscript`: the scriptlet that is executed inside the container when it is started.
- `%test`: this section is run at the very end of the bootstrapping process and validates the container during the bootstrap process.

Once the definition file is ready, and if the image file exists, then a user can run the Singularity command `bootstrap` to install the operating system into the container image.

If there is no bootstrap image already, then it can be created with the `singularity create` command:

Example

```
[root@bright82 ~]$ mkdir /cm/shared/sing-images
[root@bright82 ~]$ singularity create --size 1024 /cm/shared/sing-images/centos7.img
Creating a new image with a maximum size of 1024MiB...
Executing image create helper
Formatting image with ext3 file system
Done.
[root@bright82 ~]$
```

Note that the image must be created and bootstrapped by a privileged user, even if it is always supposed to be executed with regular user permissions. If, as is the usual case, users are not allowed to use root permissions on a cluster, then they can create and bootstrap the new image on their own computers. The image can then be transferred to the cluster.

A very simple image definition file for CentOS can look like this:

Example

```
[root@bright82 ~]$ cat centos7.def
BootStrap: yum
OSVersion: 7
MirrorURL: http://mirror.centos.org/centos-%OSVERSION/%OSVERSION/os/$basearch/
Include: yum
%post
    echo "Installing extra packages..."
    yum install vim util-linux -y
%runscript
    echo "Hello from container!"
    cat /etc/os-release
```

To bootstrap the image, the user runs `singularity bootstrap` command as root:

Example

```
[root@bright82 ~]$ module load singularity
[root@bright82 ~]$ singularity bootstrap /cm/shared/sing-images/centos7.img centos7.def
<...>
Complete!
Done.
[root@bright82 ~]$
```

The image can be placed in any directory, but it makes sense to share it among compute nodes. /cm/shared/sing-images is therefore a sensible location for keeping the container images.

The image created can then be executed as a regular binary:

Example

```
[user@bright82 ~]$ module load singularity
[user@bright82 ~]$ /cm/shared/sing-images/centos7.img
Hello from container!
NAME="CentOS Linux"
VERSION="7 (Core)"
ID="centos"
ID_LIKE="rhel fedora"
VERSION_ID="7"
PRETTY_NAME="CentOS Linux 7 (Core)"
ANSI_COLOR="0;31"
CPE_NAME="cpe:/o:centos:centos:7"
HOME_URL="https://www.centos.org/"
BUG_REPORT_URL="https://bugs.centos.org/"

CENTOS_MANTISBT_PROJECT="CentOS-7"
CENTOS_MANTISBT_PROJECT_VERSION="7"
REDHAT_SUPPORT_PRODUCT="centos"
REDHAT_SUPPORT_PRODUCT_VERSION="7"

[user@bright82 ~]$
```

The default 768MiB image size can be changed with --size option of the singularity create and singularity expand commands. The expand command increases the image size. There is no standard way of decreasing the image size.

The following example shows an image definition file that adds the /etc/services file and /bin/grep binary from the filesystem of the host, to the container image. When a user runs the image that is created, it greps the services file for arguments passed to the image:

Example

```
[root@bright82 ~]$ module load singularity
[root@bright82 ~]$ singularity create /cm/shared/sing-images/grep.img
Creating a new image with a maximum size of 768MiB...
Executing image create helper
Formatting image with ext3 file system
Done.
[root@bright82 ~]$ cat grep.def
BootStrap: yum
OSVersion: 7
MirrorURL: http://mirror.centos.org/centos-%OSVERSION/%OSVERSION/os/$basearch/
Include: grep
%setup
cp /etc/services $SINGULARITY_ROOTFS/etc/services
%runscript
exec /bin/grep $@ /etc/services

[root@bright82 ~]$ singularity bootstrap /cm/shared/sing-images/grep.img grep.def
<...>
Complete!
Executing Postbootstrap module
```

```
+ cp /etc/services /var/singularity/mnt/final/etc/services
Done.
```

The container can now be run as if it were a simple script. If a string is passed as an argument, the `/etc/services` file that is packaged inside the container is searched for the string:

Example

```
[user@bright82 ~]$ /cm/shared/sing-images/grep.img telnets
telnets      992/tcp
telnets      992/udp
[user@bright82 ~]$
```

11.2 Using MPI

The standard way to include an MPI application within the image is to install an MPI implementation RPM to the image. In this case, each file of the RPM becomes present in the image, just as in the case of the files specified separately with the `InstallFile` parameter. For example, an image can be built with the MPICH application as follows:

Example

```
[root@bright82 ~]$ cat mpich.def
RELEASE=7
DistType "redhat"
MirrorURL "http://mirror.centos.org/centos-$RELEASE/$RELEASE/os/$basearch/"
Setup
Bootstrap
InstallPkgs vim-minimal procps util-linux yum bash
InstallFile /etc/yum.repos.d/cm.repo
RunCmd yum install tcl -y
RunCmd yum install env-modules -y
RunCmd yum install cm-modules-init -y
RunCmd yum install mpich-ge-gcc-64 -y
Cleanup
[root@bright82 ~]$ singularity bootstrap /cm/shared/sing-images/mpich.img mpich.def
<...>
Cleaning repos: base extras updates
Cleaning up everything
[root@bright82 ~]$
```

The `tcp` RPM package in this example is needed to ensure proper environment modules behaviour. The environment modules are needed to simplify setting the MPICH environment.

After bootstrapping, users can use the created image without root permission:

Example

```
[user@bright82 ~]$ module load mpich/ge/gcc
[user@bright82 ~]$ mpicc ./hello_mpi.c -o hello_mpi
[user@bright82 ~]$ ./hello_mpi
Hello MPI! Process 0 of 1 on bright82
[user@bright82 ~]$ module load singularity
[user@bright82 ~]$ singularity shell /cm/shared/sing-images/mpich.img
Singularity.mpich.img> id
uid=1001(user) gid=1001(user) groups=1001(user)
Singularity.mpich.img> echo $SHELL
/bin/sh
```



```
Singularity.mpich.img> bash
Singularity.mpich.img> module load mpich/ge/gcc
Singularity.mpich.img> ./hello_mpi
Hello MPI! Process 0 of 1 on bright82
Singularity.mpich.img> exit
[user@bright82 ~]$
```

11.3 Using A Container Image With Workload Managers

Due to the nature of Singularity containers, they can be executed via a workload manager within a job script, or by passing the container image as a binary to interactive utilities, such as `srun`.

For example, in order to run MPICH-linked applications as a batch job in Slurm, the following, fairly standard, job script can be used:

Example

```
[user@bright82 ~]$ cat slurm.job
#!/bin/bash
#SBATCH --ntasks=2
module load slurm
module load mpich/ge/gcc
mpirun /cm/shared/sing-images/hello_mpi.img
[user@bright82 ~]$ sbatch slurm.job
Submitted batch job 1
[user@bright82 ~]$
```

For an interactive session:

Example

```
[user@bright82 ~]$ srun /cm/shared/sing-images/hello_openmpi.img
Hello MPI! Process 0 of 1 on node001
[user@bright82 ~]$
```

In the case of other MPI implementations, there can be different `mpirun` or similar commands required. But the idea here is to use the singularity image as a regular binary, built, for example, with `mpicc`.

11.4 Using the `singularity` Utility

The main utility that is used with Singularity containers is called `singularity`. Some of the most frequently-used and useful subcommands are the following:

- `create`: create and format an image;
- `bootstrap`: bootstrap an image from scratch;
- `shell`: start an interactive shell in a container;
- `mount`: mount a container image to directory located on host filesystem;
- `exec`: execute a command within container;
- `copy`: copy files from host into the container.

By default, the container image is mounted within the container as a read-only filesystem. The user can change this with the `-w` option passed to the `singularity` command:

Example

```
[root@bright82 ~]$ module load singularity
[root@bright82 ~]$ singularity shell /cm/shared/sing-images/mpich.img
Singularity.mpich.img> touch /etc/test
touch: cannot touch 'etc/test': Read-only file system
Singularity.mpich.img> exit
[root@bright82 ~]$ singularity shell -w /cm/shared/sing-images/mpich.img
Singularity.mpich.img> touch /etc/test
Singularity.mpich.img> exit
exit
[root@bright82 ~]$ singularity exec /cm/shared/sing-images/mpich.img ls -l /etc/test
-rw-r--r-- 1 root root 0 Aug 26 09:34 /etc/test
[user@bright82 ~]$
```

Further documentation on creating and using Singularity containers can be found at <https://www.sylabs.io/docs/>.

12

User Portal

The user portal allows users to login via a browser and view the state of the cluster themselves. The interface does not allow administration, but presents data about the system. The presentation of the data can be adjusted in many cases.

The user portal is accessible at a URL with the format of `https://<head node host name>:8081/userportal`, unless the administrator has changed it.

The first time a browser is used to login to the cluster portal, a warning about the site certificate being untrusted appears in a default Bright Cluster Manager configuration. This can safely be accepted.

The user portal by default allows a user to access the following pages via links in the left hand column:

- Overview (section 12.1)
- Workload (section 12.2)
- Nodes (section 12.3)
- OpenStack (section 12.4)
- Kubernetes (section 12.5)
- Charts (section 12.6)

12.1 Overview Page

The default Overview page allows a quick glance to convey the most important cluster-related information for users (figure 12.1):




Figure 12.1: User Portal: Overview Page

The following items are displayed on a default home page:

- a Message Of The Day. The administrator may put up important messages for users here
- links to the documentation for the cluster
- contact information. This typically shows how to contact technical support
- an overview of the cluster state, displaying some cluster parameters

12.2 Workload Page

The Workload page allows a user to see workload-related information for the cluster (figure 12.2). The columns are sortable.

https://10.2.59.58:8081/userportal/#/workload

Bright Computing cmsupport

Overview Workload Nodes Hadoop OpenStack Charts

Workload

Home / Workload

Overview Filter

Queue	Scheduler	#Nodes	Running	#Queued	#Failed	#Completed	Avg. Duration	Est. Delay
defq	slurm	networknode, node[001-004], vnode002	0	0	0	0	0	0

Jobs running Filter

JobID	Scheduler	Queue	Jobname	#Processes	Username	Status	Run time
-------	-----------	-------	---------	------------	----------	--------	----------

Figure 12.2: User Portal: Workload Page

The following two tables are displayed:

- A workload overview table
- A table displaying the current jobs running on the cluster

12.3 Nodes Page

The Nodes page shows nodes on the cluster (figure 12.3), along with some of their properties. Nodes and their properties are arranged in sortable columns.

https://10.2.59.58:8081/userportal/#/nodes

Bright Computing cmsupport

Overview Workload Nodes (selected) Hadoop OpenStack Charts

Nodes

Home / Nodes

Device information Filter

Hostname	State	Memory	Cores	CPU	Speed	GPU	NICs	BI	Category
bright71	UP	7.64 GiB	4	Intel Xeon E312xx (Sandy Bridge+)	1999 MHz		2	0	
networknode	UP	1.95 GiB	1	Intel Xeon E312xx (Sandy Bridge+)	1999 MHz		9	0	openstack-network-nodes
node001...node003	UP	1.95 GiB	1	Intel Xeon E312xx (Sandy Bridge+)	2199 MHz		5	0	openstack-compute-hosts
node004	UP	1.95 GiB	1	Intel Xeon E312xx (Sandy Bridge+)	1999 MHz		5	0	openstack-compute-hosts

Figure 12.3: User Portal: Nodes Page

The following information about the head or regular nodes is presented:

- **Hostname:** the node name
- **State:** For example, UP, DOWN, INSTALLING
- **Memory:** RAM on the node
- **Cores:** Number of cores on the node
- **CPU:** Type of CPU, for example, Dual-Core AMD Opteron™
- **Speed:** Processor speed
- **GPU:** Number of GPUs on the node, if any
- **NICs:** Number of network interface cards on the node, if any
- **IB:** Number of InfiniBand interconnects on the node, if any
- **Category:** The node category that the node has been allocated by the administrator (by default it is default)

12.4 OpenStack Page

The OpenStack page (figure 12.4) shows an overview of the virtual machines, compute hosts, network nodes, the resources used by these and their properties.




Figure 12.4: User Portal: OpenStack Page

Items shown are:

- `Total VMs up`: total number of virtual machines up
- `Total VMs with errors`: total number of virtual machines that are not running
- `Total projects`: Total number of projects
- `Total networks`: Total number of networks
- `Total subnets`: Total number of subnets
- `Total routers`: Total number of routers. These are usually interconnecting networks
- `Total users`: Total number of users
- `Compute hosts`: Compute hosts
- `Network nodes`: Network nodes
- `Projects`: The projects are listed in sortable columns, by name and UUID,
- `Cloud status text`
- `Dashboard URLs`: URLs to the clusters
- `Default project name`: by default set to `tenant-{username}`, unless the administrator has changed this.

12.5 Kubernetes Page

The Kubernetes page (figure 12.5) shows an overview of the resources available in clusters running Kubernetes.




Figure 12.5: User Portal: Kubernetes Page

The Kubernetes cluster is subset of a Bright cluster, and is the part of the Bright cluster that runs and controls pods. The items shown are:

- Name: The Kubernetes Cluster name
- Version: The Kubernetes version
- Nodes: The number of nodes in the Kubernetes cluster
- Namespaces: The number of namespaces defined for the Kubernetes cluster
- Services: The number of services that are served by the Kubernetes cluster
- Replication Controllers: The number of replication controllers that run on the Kubernetes cluster
- Persistent Volumes: The number of persistent volumes created for the pods of the Kubernetes cluster
- Persistent Volume Claims: The number of persistent volume claims created on the Kubernetes cluster

12.6 Charts Page

By default the Charts page displays the cluster occupation rate for the last hour (figure 12.6).




Figure 12.6: User Portal: Charts Page

Selecting other values is possible for:

- Workload Management Metrics: The following workload manager metrics can be viewed:
 - RunningJobs
 - QueuedJobs
 - FailedJobs
 - CompletedJobs
 - EstimatedDelay
 - AvgJobDuration
 - AvgExpFactor
- Cluster Management Metrics: The following metrics can be viewed
 - OccupationRate
 - NetworkBytesRecv
 - NetworkBytesSent
 - DevicesUp
 - NodesUp
 - TotalNodes

- TotalMemoryUsed
 - TotalSwapUsed
 - PhaseLoad
 - CPUCoresAvailable
 - GPUAvailable
 - TotalCPUUser
 - TotalCPUSystem
 - TotalCPUIidle
- Datapoints: The number of points used for the graph can be specified. The points are interpolated if necessary
- Interval (Hours): The period over which the data points are displayed

The meanings of the metrics are covered in Appendix G of the *Administrator Manual*. The Update button must be clicked to display any changes made.

13

Running Spark Jobs

13.1 What Is Spark?

Spark is an engine for processing Hadoop data. It can carry out general data processing, similar to MapReduce, but typically faster.

Spark can also carry out the following, with the associated high-level tools:

- stream feed processing with Spark Streaming
- SQL queries on structured distributed data with Spark SQL
- processing with machine learning algorithms, using MLlib
- graph computation, for arbitrarily-connected networks, with graphX

13.2 Spark Usage

13.2.1 Spark And Hadoop Modules

To run the commands in this section, a user must be able to access the right HDFS instance. This is typically ensured by the cluster administrator, who makes the correct Spark and Hadoop modules available for users. The exact modules used depend upon the instance name and the Hadoop distribution. Modules available for loading can be checked using:

```
$ module avail spark
$ module avail hadoop
```

Loading the spark module adds the spark-submit command to \$PATH. Jobs can be submitted to Spark with spark-submit.

Example

```
$ module avail spark
----- /cm/shared/modulefiles -----
spark/spark-test/Apache/1.5.1-bin-hadoop2.6
$ module load spark/spark-test/Apache/1.5.1-bin-hadoop2.6
$ which spark-submit
/cm/shared/apps/hadoop/Apache/spark-1.5.1-bin-hadoop2.6/bin/spark-submit
```

13.2.2 Spark Job Submission With spark-submit

spark-submit Usage

The spark-submit command provides options supporting the different Spark installation modes and configuration. These options and their usage can be listed with:

Example

```
$ spark-submit --help
Usage: spark-submit [options] <app jar | python file> [app arguments]
Usage: spark-submit --kill [submission ID] --master [spark://...]
Usage: spark-submit --status [submission ID] --master [spark://...]

Options:
[...]
```

A Spark job is typically submitted using the following options:

```
$ spark-submit --class <main-class> --master <master-url> --deploy-mode
<deploy-mode> [other options] <application-jar> [application-arguments]
```

The --master option: is used to specify the master URL <master-url>, which can take one of the following forms:

- `local`: Run Spark locally with one core.
- `local[n]`: Run Spark locally on *n* cores.
- `local[*]`: Run Spark locally on all the available cores.
- `spark://<hostname>:<port number>`: Connect to the Spark standalone cluster master specified by its host name and, optionally, port number. The service is provided on port 7077 by default.
- `yarn-client`: Connect to a YARN cluster in client mode. The cluster location is found based on the variables `HADOOP_CONF_DIR` or `YARN_CONF_DIR`.
- `yarn-cluster`: Connect to a YARN cluster in cluster mode. The cluster location is found based on the variables `HADOOP_CONF_DIR` or `YARN_CONF_DIR`.

The --deploy-mode option: specifies the deployment mode, <deploy-mode>, of the Spark application during job submission. The possible deployment modes are:

- `cluster`: The driver process runs on the worker nodes.
- `client`: The driver process runs locally on the host used to submit the job.

spark-submit Examples

Some `spark-submit` examples for a SparkPi submission are now shown. The jar file for this can be found under `$SPARK_PREFIX/lib/`. `$SPARK_PREFIX` is set by loading the relevant Spark module.

Example

Running a local serial Spark job:

```
$ spark-submit --master local --class org.apache.spark.examples.SparkPi \
$SPARK_PREFIX/lib/spark-examples-*.jar
```

Running a local job on 4 cores:

```
$ spark-submit --master local[4] --class org.apache.spark.examples.Spar\
kPi $SPARK_PREFIX/lib/spark-examples-*.jar
```

Running a job on a Spark standalone cluster in cluster deploy mode: The job should run on 3 nodes and the master is node001.

```
$ spark-submit --class org.apache.spark.examples.SparkPi --master spark\
://10.141.255.254:7070 --deploy-mode cluster --num-executors 3 $SPARK_P\
REFIX/lib/spark-examples-*.jar
```

Running a job on a Yarn cluster in client deploy mode:

```
$ spark-submit --class org.apache.spark.examples.SparkPi --master yarn-\
client --total-executors-cores 24 $SPARK_PREFIX/lib/spark-examples-*.jar
```

Running pyspark in standalone mode:

```
$ MASTER=local[4] pyspark
```

Running pyspark in yarn client mode:

```
$ pyspark --master yarn-client --num-executors 6 --executor-memory 4g -\
-executor-cores 12
```

Monitoring Spark Jobs

After submitting a job, it is possible to monitor its scheduler stages, tasks, memory usage, and so on. These can be viewed in the web interfaces launched by SparkContext, on port 4040 by default. The information can be viewed during job execution only.

In order to view job details after a job is finished, the user can access the web user interface of Spark's Standalone Mode cluster manager. If Spark is running on YARN, then it is also possible to view the finished job details if Spark's history server is running. The history server is configured by the cluster administrator.

In both cases, the job should log events over the course of its lifetime.

Spark Documentation

The official Spark documentation is available at <http://spark.apache.org/docs/latest/>.

14

Using OpenStack

The cluster administrator can have Bright Cluster Manager configured in two ways with OpenStack.

1. **Bright-managed instances:** This has the cluster providing virtual Bright nodes, called *vnodes* for users. Vnodes are not really that different from regular nodes as far as the end user is concerned, and in any case the cluster administrator typically sets up how they can be used. The end user typically simply gets on with using them without having to think much about it.
2. **user instances:** This has the cluster provide the user with the ability to start a instance under OpenStack. The instance can be from a variety of pre-packaged cloud images, and can be handled with the standard OpenStack commands or with the OpenStack Horizon dashboard.

Setting up a user instance is therefore what this chapter is mainly about.

14.1 User Access To OpenStack

The end user with a user name and password to access their Bright account, is typically given a user name and password for the OpenStack account.

The OpenStack account password may be:

- independent of the Bright account password, and use a different password.
- independent of the Bright account password, but initially use the same password. The passwords can be made different by the user, or indeed kept the same by the user.
- the same as the Bright account password.

Which of these three options it is depends on how the cluster administrator has configured the system.

14.2 Getting A User Instance Up

By default, an OpenStack user, *fred* for example, can log in as an OpenStack user. However, unless something extra has been prepared, a user that logs in at this point has no instances up yet. *fred* typically wants an OpenStack system with running instances.

OpenStack can be configured in an very large number of ways. The user should check with the cluster administrator if the configured OpenStack deployment allows the steps that follow to be carried out, or if they may need some workarounds or modifications. If the cluster administrator has not customized the cluster, then getting an instance up and running can be done as in the following sections.

14.2.1 Making An Image Available In OpenStack

A handy source of available images is at <http://docs.openstack.org/image-guide/obtain-images.html>. The URI lists where images for major, and some minor distributions, can be picked up from.

Cirros is one of the distributions listed there. It is a distribution that aims at providing a small, but reasonably functional cloud instance. The Cirros image listed there can therefore be used for setting up a small standalone instance, suitable for an m1.xtiny flavor, which is useful for basic testing purposes.

Installing The Image Using The openstack Utility

If the qcow2 image file `cirros-0.3.4-x86_64-disk.img`, 13MB in size, is picked up from the site and placed in the local directory of the user, then an image `cirros034` can be set up and made publicly available by user by using the `openstack image create` command as follows:

Example

```
[fred@bright82 ~]$ wget http://download.cirros-cloud.net/0.3.4/cirros-0.3.4-x86_64-disk.img
...
2016-05-10 14:19:43 (450 KB/s) - `cirros-0.3.4-x86_64-disk.img' saved [13287936/13287936]
[fred@bright82 ~]$ openstack image create --disk-format qcow2 --public --file\
  cirros-0.3.4-x86_64-disk.img cirros034
```

The `openstack` command in the preceding example assumes that the `.openstackrc` file has been generated, and sourced, in order to provide the OpenStack environment. The cluster administrator typically configures the system so that the `.openstackrc` file is automatically generated for the user, so that it can be sourced with:

Example

```
[fred@bright82 ~]$ . .openstackrc
```

Sourcing means running the file so that the environment variables in the file are set in the shell on return. The shell in which fred is logged into either needs the environment to be in place for OpenStack actions to work, or it needs the relevant options to be provided by fred to the `oslc` utility during execution.

If all goes well, then the image is installed and can be seen by the user, via OpenStack Horizon, by navigation to the Images pane, or using the URI `http://<IP address>:10080/dashboard/project/images/` directly (figure 14.1).




Figure 14.1: Images Pane In Horizon

Installing The Image Using Horizon

Alternatively, instead of using the `oslc` utility, the image can also be installed by the user using the OpenStack Horizon web interface directly. The Horizon procedure to install the image is described next:

Clicking on the **Create Image** button of the **Images** pane launches a pop-up dialog. Within the dialog, a name for the image for OpenStack users can be set, the disk format of the image can be selected, the HTTP URL from where the image can be picked up can be specified, and the image can be kept private or made public (figure 14.2).




Figure 14.2: Images Pane—Create Image Dialog

The State Of The Installed Image

After the image has been installed, it is available for launching instances by `fred`. If the checkbox for **Public** was ticked in the previous dialog, then other OpenStack users can also use it to launch their instances. The image properties can then be viewed by allowed OpenStack users—for example by using OpenStack Horizon, by clicking through for **Image Details**.

However, although the image is available, it is not yet ready for launch. It first needs some networking components.

14.2.2 Creating The Networking Components For The OpenStack Image To Be Launched

The networking components are needed due to a default policy of network isolation. Only after the components are in place can the image run within OpenStack on a virtual machine.

Creating The Network With Horizon

A network can be created in OpenStack Horizon using the **Network** part of the navigation menu, then selecting **Networks**. Clicking on the **Create Network** button on the right hand side opens up the **Create Network** dialog box.

In the first screen of the dialog, the network for `fred` can be given the unimaginative name of, for example, `frednet` (figure 14.3):




Figure 14.3: End User Network Creation

Similarly, in the next screen a subnet called `fredsubnet` can be configured, along with a gateway address for the subnet (figure 14.4):




Figure 14.4: End User Subnet Creation

In the next screen (figure 14.5):

- a range of addresses on the subnet is earmarked for DHCP assignment to devices on the subnet
- a DNS address is set
- special routes for hosts can be set




Figure 14.5: End User DHCP, DNS, And Routes

At the end of a successful network creation, when the dialog box has closed, the screen should look similar to figure 14.6:




Figure 14.6: End User Node Network Configuration Result

The State Of The Image With Its Network Configured

At this point, the image can be launched, for example using Horizon's Compute resource in the navigation panel, then choosing the Instances pane, and then clicking on the Launch Instance button. On

launching, the image will run. However, it will only be accessible via the OpenStack console, which has some quirks, such as only working well in fullscreen mode in some browsers.

It is more pleasant and practical to login via a terminal client such as ssh. How to configure this is described next.

14.2.3 Accessing The Instance Remotely With A Floating IP Address

Remote access from outside the cluster is typically carried out with a floating IP address, from a pool of pre-defined floating IP address. The configuration is as follows:

Router Configuration For A Floating IP Address

Router configuration for a floating IP address with Horizon: A router can be configured from the Network part of the navigation menu, then selecting Routers. Clicking on the Create Router button on the right hand side opens up the Create Router dialog box (figure 14.7):




Figure 14.7: End User Router Creation

The router can be given a name, and connected to the external network of the cluster.

Next, an extra interface for connecting to the network of the instance can be added by clicking on the router name, which brings up the Router Details page. Within the Interfaces subtab, the Add Interface button on the right hand side opens up the Add Interface dialog box (figure 14.8):




Figure 14.8: End User Router Interfaces Creation

After connecting the network of the instance, the router interface IP address should be the gateway of the network that the instance is running on (figure 14.9):




Figure 14.9: End User Router Interface Screen After Router Configuration

The state of the router after floating IP address configuration: To check the router is reachable from the head node, the IP address of the router interface connected to the cluster external network should show a ping response.

The IP address can be seen in the Overview subtab of the router (figure 14.10):




Figure 14.10: End User Router Details After Router Configuration

A ping behaves as normal for the interface on the external network:

Example

```
[fred@bright82 ~]$ ping -c1 192.168.100.13
PING 192.168.100.13 (192.168.100.13) 56(84) bytes of data.
64 bytes from 192.168.100.13: icmp_seq=1 ttl=64 time=0.383 ms

--- 192.168.100.13 ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 0.383/0.383/0.383/0.000 ms
```

Security group rules to allow a floating IP address to access the instance: The internal interface to the instance is still not reachable via the floating IP address. That is because by default there are security group rules that set up iptables to restrict ingress of packets across the network node. A network node is a routing node that is part of Bright Cluster Manager OpenStack.

The rules can be managed by accessing the Compute resource, then selecting the Access & Security page. Within the Security Groups subtab there is a Manage Rules button. Clicking the button brings up the Manage Security Group Rules table (figure 14.11):




Figure 14.11: Security Group Rules Management

Clicking on the Add Rule button brings up a dialog. To let incoming pings work, the rule All ICMP can be added. Further restrictions for the rule can be set in the other fields of the dialog for the rule (figure 14.12).




Figure 14.12: Security Group Rules Management—Adding A Rule

Floating IP address association with the instance: The floating IP address can now be associated with the instance. One way to do this is to select the Compute resource in the navigation window, and select Instances. In the Instances window, the button for the instance in the Actions column allows an IP address from the floating IP address pool to be associated with the IP address of the instance (figure 14.13).




Figure 14.13: Associating A Floating IP Address To An Instance

After association, the instance is pingable from the external network of the head node.

Example

```
[fred@bright82 ~]$ ping -c1 192.168.100.10
PING 192.168.100.10 (192.168.100.10) 56(84) bytes of data:
64 bytes from 192.168.100.10: icmp_seq=1 ttl=63 time=1.54 ms

--- 192.168.100.10 ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 1.544/1.544/1.544/0.000 ms
```

If SSH is allowed in the security group rules instead of ICMP, then fred can run ssh and log into the Cirros instance, using the default username/password cirros/cubswin:)

Example


```
[fred@bright82 ~]$ ssh cirros@192.168.100.10
cirros@192.168.100.10's password:
$
```

Setting up SSH keys: Setting up SSH key pairs for a user fred allows a login to be done using key authentication instead of passwords. The standard OpenStack way of setting up key pairs is to either import an existing public key, or to generate a new public and private key. This can be carried out from the Compute resource in the navigation window, then selecting the Access & Security page. Within the Key Pairs subtab there are the Import Key Pair button and the Create Key Pair button.

- **importing a key option:** For example, user fred created in Bright Cluster Manager as in this chapter has his public key in /home/fred/.ssh/id_dsa.pub on the head node. Pasting the text of the key into the import dialog, and then saving it, means that the user fred can now login as the user cirros without being prompted for a password from the head node. This is true for images that are cloud instances, of which the cirros instance is an example.

- **creating a key pair option:** Here a pair of keys is generated for a user. A PEM container file with just the private key *<PEM file>*, is made available for download to the user, and should be placed in a directory accessible to the user, on any host machine that is to be used to access the instance. The corresponding public key is stored by OpenStack's Keystone, and the private key discarded by the generating machine. The downloaded private key should be stored where it can be accessed by `ssh`, and should be kept read and write only, for the user only. If its permissions have changed, then running `chmod 600 <PEM file>` on it will make it compliant. The user can then login to the instance using, for example, `ssh -i <PEM file> cirros@192.168.100.10`, without being prompted for a password.

The `openstack keypair` options are the `openstack` utility equivalent for the preceding Horizon operations.



MPI Examples

A.1 “Hello world”

A quick application to test the MPI libraries and the network.

```
/*
  ``Hello World'' Type MPI Test Program
*/
#include <mpi.h>
#include <stdio.h>
#include <string.h>

#define BUFSIZE 128
#define TAG 0

int main(int argc, char *argv[])
{
    char idstr[32];
    char buff[BUFSIZE];
    int numprocs;
    int myid;
    int i;
    MPI_Status stat;

    /* all MPI programs start with MPI_Init; all 'N' processes exist thereafter */
    MPI_Init(&argc,&argv);
    MPI_Comm_size(MPI_COMM_WORLD,&numprocs); /* find out how big the SPMD world is */
    MPI_Comm_rank(MPI_COMM_WORLD,&myid); /* and this processes' rank is */

    /* At this point, all the programs are running equivalently, the rank is used to
       distinguish the roles of the programs in the SPMD model, with rank 0 often used
       specially... */
    if(myid == 0)
    {
        printf("%d: We have %d processors\n", myid, numprocs);
        for(i=1;i<numprocs;i++)
        {
            sprintf(buff, "Hello %d! ", i);
            MPI_Send(buff, BUFSIZE, MPI_CHAR, i, TAG, MPI_COMM_WORLD);
        }
        for(i=1;i<numprocs;i++)
        {
```

```

    MPI_Recv(buff, BUFSIZE, MPI_CHAR, i, TAG, MPI_COMM_WORLD, &stat);
    printf("%d: %s\n", myid, buff);
}
}
else
{
    /* receive from rank 0: */
    MPI_Recv(buff, BUFSIZE, MPI_CHAR, 0, TAG, MPI_COMM_WORLD, &stat);
    sprintf(idstr, "Processor %d ", myid);
    strcat(buff, idstr);
    strcat(buff, "reporting for duty\n");
    /* send to rank 0: */
    MPI_Send(buff, BUFSIZE, MPI_CHAR, 0, TAG, MPI_COMM_WORLD);
}

/* MPI Programs end with MPI Finalize; this is a weak
   synchronization point */
MPI_Finalize();
return 0;
}

```

A.2 MPI Skeleton

The sample code below contains the complete communications skeleton for a dynamically load balanced head/compute node application. Following the code is a description of some of the functions necessary for writing typical parallel applications.

```

include <mpi.h>
#define WORKTAG    1
#define DIETAG     2
main(argc, argv)
int  argc;
char *argv[];
{
    int      myrank;
    MPI_Init(&argc, &argv);  /* initialize MPI */
    MPI_Comm_rank(
        MPI_COMM_WORLD, /* always use this */
        &myrank);        /* process rank, 0 thru N-1 */
    if (myrank == 0) {
        head();
    } else {
        computenode();
    }
    MPI_Finalize();        /* cleanup MPI */
}

head()
{
    int      ntasks, rank, work;
    double   result;
    MPI_Status status;
    MPI_Comm_size(
        MPI_COMM_WORLD, /* always use this */
        &ntasks);        /* #processes in application */

```

```

/*
 * Seed the compute nodes.
 */
    for (rank = 1; rank < ntasks; ++rank) {
        work = /* get_next_work_request */;
        MPI_Send(&work,          /* message buffer */
        1,                      /* one data item */
        MPI_INT,                /* data item is an integer */
        rank,                   /* destination process rank */
        WORKTAG,                /* user chosen message tag */
        MPI_COMM_WORLD); /* always use this */
    }

/*
 * Receive a result from any compute node and dispatch a new work
 * request work requests have been exhausted.
 */
    work = /* get_next_work_request */;
    while (/* valid new work request */) {
        MPI_Recv(&result,        /* message buffer */
        1,                      /* one data item */
        MPI_DOUBLE,             /* of type double real */
        MPI_ANY_SOURCE, /* receive from any sender */
        MPI_ANY_TAG,           /* any type of message */
        MPI_COMM_WORLD, /* always use this */
        &status);              /* received message info */
        MPI_Send(&work, 1, MPI_INT, status.MPI_SOURCE,
        WORKTAG, MPI_COMM_WORLD);
        work = /* get_next_work_request */;
    }

/*
 * Receive results for outstanding work requests.
 */
    for (rank = 1; rank < ntasks; ++rank) {
        MPI_Recv(&result, 1, MPI_DOUBLE, MPI_ANY_SOURCE,
        MPI_ANY_TAG, MPI_COMM_WORLD, &status);
    }

/*
 * Tell all the compute nodes to exit.
 */
    for (rank = 1; rank < ntasks; ++rank) {
        MPI_Send(0, 0, MPI_INT, rank, DIETAG, MPI_COMM_WORLD);
    }
}

computenode()
{
    double          result;
    int             work;
    MPI_Status      status;
    for (;;) {
        MPI_Recv(&work, 1, MPI_INT, 0, MPI_ANY_TAG,
        MPI_COMM_WORLD, &status);
    }
}

```

```

* Check the tag of the received message.
*/
    if (status.MPI_TAG == DIETAG) {
        return;
    }
    result = /* do the work */;
    MPI_Send(&result, 1, MPI_DOUBLE, 0, 0, MPI_COMM_WORLD);
}
}

```

Processes are represented by a unique rank (integer) and ranks are numbered 0, 1, 2, ..., N-1. MPI_COMM_WORLD means all the processes in the MPI application. It is called a communicator and it provides all information necessary to do message passing. Portable libraries do more with communicators to provide synchronisation protection that most other systems cannot handle.

A.3 MPI Initialization And Finalization

As with other systems, two functions are provided to initialize and clean up an MPI process:

```

MPI_Init(&argc, &argv);
MPI_Finalize( );

```

A.4 What Is The Current Process? How Many Processes Are There?

Typically, a process in a parallel application needs to know who it is (its rank) and how many other processes exist.

A process finds out its own rank by calling:

```

MPI_Comm_rank( ):
Int myrank;
MPI_Comm_rank(MPI_COMM_WORLD, &myrank);

```

The total number of processes is returned by MPI_Comm_size():

```

int nprocs;
MPI_Comm_size(MPI_COMM_WORLD, &nprocs);

```

A.5 Sending Messages

A message is an array of elements of a given data type. MPI supports all the basic data types and allows a more elaborate application to construct new data types at runtime. A message is sent to a specific process and is marked by a tag (integer value) specified by the user. Tags are used to distinguish between different message types a process might send/receive. In the sample code above, the tag is used to distinguish between work and termination messages.

```

MPI_Send(buffer, count, datatype, destination, tag, MPI_COMM_WORLD);

```

A.6 Receiving Messages

A receiving process specifies the tag and the rank of the sending process. MPI_ANY_TAG and MPI_ANY_SOURCE may be used optionally to receive a message of any tag and from any sending process.

```

MPI_Recv(buffer, maxcount, datatype, source, tag, MPI_COMM_WORLD, &status);

```

Information about the received message is returned in a status variable. The received message tag is `status.MPI_TAG` and the rank of the sending process is `status.MPI_SOURCE`. Another function, not used in the sample code, returns the number of data type elements received. It is used when the number of elements received might be smaller than `maxcount`.

```
MPI_Get_count(&status, datatype, &elements);
```

A.7 Blocking, Non-Blocking, And Persistent Messages

`MPI_Send` and `MPI_Receive` cause the running program to wait for non-local communication from a network. Most communication networks function at least an order of magnitude slower than local computations. When an MPI process has to wait for non-local communication CPU cycles are lost because the operating system has to block the process, then has to wait for communication, and then resume the process.

An optimal efficiency is usually best achieved by overlapping communication and computation. *Blocking* messaging functions only allow one communication to occur at a time. *Non-blocking* messaging functions allow the application to initiate multiple communication operations, enabling the MPI implementation to proceed simultaneously. *Persistent* non-blocking messaging functions allow a communication state to persist, so that the MPI implementation does not waste time on initializing or terminating a communication.

A.7.1 Blocking Messages

In the following example, the communication implementation executes in a sequential fashion causing each process, `MPI_Recv`, then `MPI_Send`, to block while waiting for its neighbor:

Example

```
while (looping) {
    if (i_have_a_left_neighbor)
        MPI_Recv(inbuf, count, dtype, left, tag, comm, &status);
    if (i_have_a_right_neighbor)
        MPI_Send(outbuf, count, dtype, right, tag, comm);
    do_other_work();
}
```

MPI also has the potential to allow both communications to occur simultaneously, as in the following communication implementation example:

A.7.2 Non-Blocking Messages

Example

```
while (looping) {
    count = 0;
    if (i_have_a_left_neighbor)
        MPI_Irecv(inbuf, count, dtype, left, tag, comm, &req[count++]);
    if (i_have_a_right_neighbor)
        MPI_Isend(outbuf, count, dtype, right, tag, comm, &req[count++]);
    MPI_Waitall(count, req, &statuses);
    do_other_work();
}
```

In the example, `MPI_Waitall` potentially allows both communications to occur simultaneously. However, the process as shown is blocked until both communications are complete.

A.7.3 Persistent, Non-Blocking Messages

A more efficient use of the waiting time means to carry out some other work in the meantime that does not depend on that communication. If the same buffers and communication parameters are to be used in each iteration, then a further optimization is to use the MPI persistent mode. The following code instructs MPI to set up the communications once, and communicate similar messages every time:

Example

```
int count = 0;
if (i_have_a_left_neighbor)
    MPI_Recv_init(inbuf, count, dtype, left, tag, comm, &req[count++]);
if (i_have_a_right_neighbor)
    MPI_Send_init(outbuf, count, dtype, right, tag, comm, &req[count++]);
while (looping) {
    MPI_Startall(count, req);
    do_some_work();
    MPI_Waitall(count, req, &statuses);
    do_rest_of_work();
}
```

In the example, `MPI_Send_init` and `MPI_Recv_init` perform a persistent communication initialization.

B

Compiler Flag Equivalence

The following table is an overview of some of the compiler flags that are equivalent or almost equivalent.

PGI	Pathscale	Cray	Intel	GCC	Explanation
-fast	-O3	default	default	-O3 -ffast-math	Produce high level of optimization
-mp=nonuma	-mp	-Oomp (default)	-openmp	-fopenmp	Activate OpenMP directives and pragmas in the code
-byteswapio	-byteswapio	-h byteswapio	-convert big_endian	-fconvert=swap	Read and write Fortran unformatted data files as big-endian
-Mfixed	-fixedform	-f fixed	-fixed	-ffixed-form	Process Fortran source using fixed form specifications.
-Mfree	-freeform	-f free	-free	-ffree-form	Process Fortran source using free form specifications.
-V	-dumpversion	-V	--version	--version	Dump version.
N/A	-zerouv	-h zero	N/A	-finit-local-zero	Zero fill all uninitialized variables.
		-e m			Creates .mod files to hold Fortran90 module information for future compiles.
		-j <dir_name>			Specifies the directory <dir_name> to which .mod files are written when the -e m option is specified